

FLEX^{lm} End Users Guide

Version 7.2

GLOBEtrotter Software, Inc.

San Jose, CA 95125


Voice: (408) 445-8100

Fax: (408) 445-7760

Email: info@globes.com

Web: <http://www.globetrotter.com>

December 2000





COPYRIGHT

© 1995-2000 GLOBEtrotter Software, Inc. All Rights Reserved.

GLOBEtrotter Software products contain certain confidential information of GLOBEtrotter Software, Inc. Use of this copyright notice is precautionary and does not imply publication or disclosure. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language in any form by any means without the written permission of GLOBEtrotter Software, Inc.

TRADEMARK

GLOBEtrotter and FLEXlm are registered trademarks of GLOBEtrotter Software, Inc. “Electronic Commerce for Software,” “Electronic Licensing,” GLOBEtrotter Software, Globetrotter Software, GTweb*Licensing*, “No Excuses Licensing,” “Policy in the License, SAMreport, SAMsolutions, SAMsuite, SAMwrap, and the tilted compass image are all trademarks of GLOBEtrotter Software, Inc. All other brand and product names mentioned herein are the trademarks and registered trademarks of their respective owners.

RESTRICTED RIGHTS LEGEND

Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights of Technical Data and Computer Software clause of DFARS 252.227-0713 and FAR52.227-19 and/or applicable Federal Acquisition Regulation protecting the commercial ownership rights of independently developed commercial software.

Printed in the USA.
December 2000

Contents

Chapter 1	Welcome to FLEXlm	8
1.1	Versions of FLEXlm	8
1.2	How to Use This Manual	8
1.3	Related Documents from GLOBEtrötter Software	10
Chapter 2	Introduction and Overview	12
2.1	Introduction to FLEXlm	12
2.2	FLEXlm Components	12
2.3	The License Request Process	14
2.4	Configuring FLEXlm	15
2.5	Getting Started Checklist	15
Chapter 3	The License File	18
3.1	Specifying Location of the License File	18
3.2	License File Format	22
3.3	Sample License File	34
3.4	Types of License Files	34
3.5	Decimal Format	36
3.6	License File Order	37
Chapter 4	Multiple License Files	38
4.1	Overview of Combining License Files	38
4.2	Using LM_LICENSE_FILE License File List	41
Chapter 5	Selecting Server Nodes	42
5.1	Resources Used by the Server	42
5.2	Remote Mounted Disks	44
5.3	Redundant Servers	45
5.4	Counted vs. Uncounted Licenses	47

Chapter 6	The Options File	48
6.1	Creating an Options File	48
6.2	Options File Syntax	49
6.3	How the Vendor Daemon Uses the Options File	58
6.4	Rules of Precedence in Options Files	58
6.5	Options File Examples	59
Chapter 7	License Administration Tools	62
7.1	Running Administration Tools	62
7.2	Universal lmutil Arguments	63
7.3	lmcksum	64
7.4	lmdiag	64
7.5	lmdown	66
7.6	lmgrd	67
7.7	lmhostid	69
7.8	lminstall	70
7.9	lmnewlog	71
7.10	lmremove	71
7.11	lmreread	73
7.12	lmstat	74
7.13	lmswitchr	76
7.14	lmver	76
7.15	License Administration Tools—LMTOOLS for Windows	77
Appendix A	Hostids for FLEXlm-Supported Machines	78
A.1	Hostid Formats	78
A.2	Expected FLEXlm Hostids	79
A.3	Special FLEXlm Hostids	80
Appendix B	Troubleshooting Guide	82
B.1	General Debugging Hints	82
B.2	FLEXLM_DIAGNOSTICS	83
B.3	FLEXlm Troubleshooting List	85
Appendix C	FLEXlm Environment Variables	92
C.1	How to Set Environment Variables	92
C.2	Environment Variables	93

Appendix D	Frequently Asked Questions	94
D.1	License File Questions	94
D.2	FLEXlm Versions	95
D.3	Using FLEXlm	96
D.4	Windows Questions	99
Appendix E	FLEXlm Error Codes	100
E.1	Error Message Format	100
E.2	Error Code Descriptions	101
Appendix F	The Debug Log File	108
F.1	Informational Messages	108
F.2	Configuration Problem Messages	110
F.3	Daemon Software Error Messages	111
Appendix G	FLEXlm Versions	114
G.1	Version Compatibility and Components	114
G.2	How to Tell the License File Version	115
Index	120

Welcome to FLEXlm

FLEXlm[®] is the *de facto* standard network license manager used by over 2000 leading software vendors to control the use of their software products. If you are a system administrator or user, chances are one or more of the products currently on your network is licensed by FLEXlm.

This manual explains FLEXlm from an end user standpoint and describes how to use the tools which are part of the standard FLEXlm distribution kit. GLOBEtrouter Software also provides the SAMsuite[™] asset management tool for more advanced license server control and reporting. Please contact GLOBEtrouter Software by email at info@globes.com or on the Internet at <http://www.globetrouter.com> for more information about SAMsuite.

Keep in mind that certain topics (such as password encryption) are vendor-specific and proprietary so we cannot document them in any detail. Also, because FLEXlm does not enforce a particular licensing strategy, each vendor's implementation can have subtle differences. If you do not find out what you need to know here, you should contact your vendor's technical support group.

1.1 Versions of FLEXlm

This manual covers features of interest to license administrators and end users in FLEXlm versions 1.0 through 7.2.

1.2 How to Use This Manual

This manual is written for two different audiences: the license administrator and the end user.

1.2.1 License Administrator

If you are a license administrator, read these chapters:

This chapter:	Explains:
Welcome to FLEXlm	FLEXlm basics: license manager and vendor daemons; the license file; configuring FLEXlm; the license request process.
The License File	The license file format; setting the path at start-up; different types of licensing policies.
Multiple License Files	Using license files from independent software vendors.
Selecting Server Nodes	Selecting which machines will run the license servers; resources required by the servers; multiple servers; quorums; redundant servers.
The Options File	Creating and editing the options file.
License Administration Tools	Managing FLEXlm using GLOBEtrouter-supplied utilities.

In addition, you can refer to Appendix B, “Troubleshooting Guide,” which contains a list of common problems and their solutions and Appendix D, “Frequently Asked Questions.”

1.2.2 End User

If you are an end user, read these chapters:

This chapter:	Explains:
Welcome to FLEXlm	FLEXlm basics: license and vendor daemons; the license file; configuring FLEXlm; the license request process.
The License File	The license file format; setting the path at start-up; different types of licensing policies.

In addition, you can refer to Appendix B, “Troubleshooting Guide,” which contains a list of common problems and their solutions.

1.3 Related Documents from GLOBEtrotter Software

The *SAMsuite Users Guide* describes the *SAMsuite* license administration tool for managing *FLEXlm*-enabled applications, and the *SAMwrap Users Guide* describes *SAMwrap* for administrators who wish to provide *FLEXlm* license management for applications shipped without embedded license management.

The *FLEXlm Programmers Guide* and *FLEXlm Reference Manual* are for programmers responsible for incorporating *FLEXlm* into their products.

Introduction and Overview

This chapter explains the basics of floating (network) licensing and gives a quick overview of the components of FLEXlm. It explains where license administrators have control and where end users have control. Section 2.5, “Getting Started Checklist,” tells both license administrators and end users how to start managing FLEXlm.

2.1 Introduction to FLEXlm

FLEXlm is the most popular license manager used in the software industry. FLEXlm is best known for its ability to allow software licenses to be available (or float) anywhere on a network, instead of being tied to specific machines. Floating licensing benefits both users and license administrators. Users can make more efficient use of fewer licenses by sharing them on the network. License administrators can control who uses the licensed application and the node(s) where the licenses will be available. See Section 3.4, “Types of License Files,” for details about the different licensing models supported by FLEXlm.

2.2 FLEXlm Components

The four main components of FLEXlm are:

- License manager daemon
- Vendor daemon
- License file
- Application program

2.2.1 The License Manager Daemon (lmgrd)

The *license manager daemon* (lmgrd) handles the initial contact with the client application programs, passing the connection on to the appropriate vendor daemon. It also starts and restarts the vendor daemons. FLEXlm permits multiple redundant license manager daemons on three server nodes,

allowing you to make your license available if any two of the three server nodes is running. Redundancy can be achieved with three-server redundant servers or by using a license file list with any number of servers.

Note: `lmgrd` is not present on VMS or Netware systems.

2.2.2 The Vendor Daemon

In *FLEXlm*, licenses are granted by running processes (unless they're node-locked, uncounted licenses, in which case they need only read the license file to run). There is one process for each vendor who has a *FLEXlm*-licensed product on the network. This process is called the *vendor daemon*. The vendor daemon keeps track of how many licenses are checked out, and who has them. If the vendor daemon terminates for any reason, all users lose their licenses (though this does not mean the applications suddenly stop running). Users normally regain their license automatically when `lmgrd` restarts the vendor daemon, though they may exit if the vendor daemon remains unavailable.

Client programs communicate with the vendor daemon, usually through TCP/IP network communications. The client application and the daemon processes (the *license server*) can run on separate nodes on your network, across any size wide-area network. Also, the format of the traffic between the client and the vendor daemon is machine independent, allowing for heterogeneous networks. This means the license server and the computer running an application can be either different hardware platforms or even different operating systems (Windows and UNIX, for example).

2.2.3 The License File

Licensing data is stored in a text file called the license file. The license file is created by the software vendor, and edited and installed by the license administrator. It contains information about the server nodes and vendor daemons, and at least one line of data (called *FEATURE* or *INCREMENT* lines) for each licensed product. Each *FEATURE* line contains a license key or signature based on the data in that line, the hostids specified in the *SERVER* line(s), and other vendor-specific data.

In some environments, the licensing information for several vendors may be combined into a single license file.

Most applications have an expected location for the license file, documented by that application. End users can usually override this location by setting the environment variable `LM_LICENSE_FILE` to point elsewhere, or by following

instructions supplied with the licensed application. If your site has software from multiple vendors with incompatible license files (due to different sets of servers), you can keep the data in separate files and set the `LM_LICENSE_FILE` variable to reference multiple files.

It's strongly recommended that you keep a link (on UNIX) or copy of the license file in the vendor's expected license location, so that users will not need to set `LM_LICENSE_FILE` to run their applications. If the licenses are counted (floating) this license should have a `USE_SERVER` line directly after the `SERVER` line. For details, see Chapter 3, "The License File." See also Appendix C, "FLEXlm Environment Variables."

2.2.4 The Application Program

The application program using FLEXlm is linked with the program module (called the FLEXlm client library) that provides the communication with the license server. On Windows, this module is called `lmgrxxx.dll`, where `xxx` indicates the FLEXlm version. During execution, the application program communicates with the vendor daemon to request a license.

2.3 The License Request Process

When you run a counted FLEXlm-licensed application, the following occurs:

1. The license module in the client application finds the license file, which includes the host name of the license server node and port number of the license manager daemon, `lmgrd`.
2. The client establishes a connection with the license manager daemon (`lmgrd`) and tells it what vendor daemon it needs to talk to.
3. `lmgrd` determines which machine and port correspond to the master vendor daemon and sends that information back to the client.
4. The client establishes a connection with the specified vendor daemon and sends its request for a license.
5. The vendor daemon checks in its memory to see if any licenses are available and sends a grant or denial back to the client.
6. The license module in the application grants or denies use of the feature, as appropriate.

Uncounted features (where the license count is 0) do not require a server, and the FLEXlm client library routines in the application grant or deny usage based solely upon the license contents.

2.4 Configuring FLEXlm

Most of the parameters of FLEXlm are configurable by the license administrator. The license administrator can set the:

- Location of the license file (though it's recommended that a copy or link of the license remains at the location where the application expects it)
- Location of all executables
- Location of all log files
- TCP/IP port number used by the license manager process, `lmgrd`

In addition, the license administrator can reserve licenses for specific users, nodes, or groups, and control other license-related options. Changing parameters is discussed in Chapter 6, “The Options File.”

Note: Refer to your vendor's documentation before attempting to change file names, locations, or contents.

2.5 Getting Started Checklist

The following sections provide a quick overview of how to set up and use licensing for FLEXlm-licensed products. By scanning the list, you should be able to quickly find the areas of interest. Cross-references point to more details in other parts of this manual.

2.5.1 Installing Licensed Software

As a license administrator you are responsible for setting up licensing on your system or network. This section tells you how to do that. If you are an end user of the application and you will not be involved in installing it, then go to Section 2.5.2, “Notes for End Users.”

Remember that the installation guide for your application software is the final word on installing and configuring FLEXlm. Generally, however, installing FLEXlm licensing requires the following steps:

1. Select your license server nodes and get their hostids. See Appendix A, “Hostids for FLEXlm-Supported Machines.”
2. Give the hostids to your software vendor and get a license file (or the data to enter in the license file) in return.
3. Consider combining the new license file with any existing license files. See Chapter 4, “Multiple License Files.”

4. Determine if an options file is desired, and if so, set it up.
5. Determine where to install the FLEX lm utility programs such as `lmgrd` and `lmutil` (`lmstat/lmdown/etc.`) and install them, unless your vendor's installation script does so for you.
6. Start `lmgrd` (the license manager daemon) manually; you may also want to set it up to start automatically at boot time. See Section 3.1.1, "Starting the License Server at System Startup."

These steps are discussed briefly below, with cross-references to the appropriate locations for more detail.

LICENSE SERVER NODE AND HOSTIDS

Before running any FLEX lm -licensed program using floating licenses, you will need to set up your license server node (or nodes). You must select which node or nodes to run your license servers on and provide the hostids of those machines to your software vendor. For pointers on selecting your server machine, see Chapter 5, "Selecting Server Nodes."

You can get the hostid of the server machine by running FLEX lm 's `lmhostid` utility on that machine. If you don't have `lmhostid`, you can get the hostid of your machine by using the appropriate command as described in Appendix A, "Hostids for FLEX lm -Supported Machines."

Using the hostid of your server machines, your vendor will send you a license file that enables their application software.

LICENSE FILES AND LMGRD

Once you have received a license file from your vendor, you must install it on your system and start up the license manager daemon, `lmgrd`.

- Your software vendor may have selected a default location for your license file. If not, you can use any location you wish. For more details, see Chapter 3, "The License File."
- To start `lmgrd` automatically at boot time, you will have to modify your system files (UNIX) or use LMTOOLS (Windows). For details, see Section 3.1.1, "Starting the License Server at System Startup."

ADMINISTRATION TOOLS

GLOBEtrouter Software supplies administration tools to your software vendor. The vendor usually includes them with their product. The recommended location for the tools is `/usr/local/bin` (UNIX), `C:\flexlm` (Windows),

or `SYS$COMMON:[SYSMGR]` (VMS), but you can install them in a different location (or not at all). See Chapter 7, “License Administration Tools,” for more information.

OPTIONS FILES

The options file controls various options such as reservations and timeouts of licenses. Most users run without an options file, but you may decide you want to use some options. For example, many administrators use an option to limit the quantity and content of logged messages. To set up an options file, see Chapter 6, “The Options File.”

2.5.2 Notes for End Users

As a user of a FLEX lm -licensed application, you may need to know a few things to use the system effectively. The main things you need to know are:

- How to tell an application which license file to use
- How to query the system to find out who is using a license

HOW TO SPECIFY A LICENSE FILE

The license file determines what features are available to a program. It also contains information telling the application how to connect to the license server.

For information about the standard way of specifying a license file for an application, see Chapter 3, “The License File.”

GETTING INFORMATION ABOUT LICENSES

To find out who is using a license run `lmstat`, described in Chapter 7, “License Administration Tools.”

The License File

The license file contains all site-specific information required by FLEXlm. This information includes:

- Server names and hostids
- Vendor names and paths to vendor daemon executables
- Feature information

In general, the license file, or a copy of it, must be accessible to every machine that runs a FLEXlm-licensed application, and each machine designated as a license server. If the license file contains counted (also called “floating”) licenses, before you can use the application you have to start the license manager daemon (`lmgrd`) using the following syntax:

```
lmgrd -c license_file_path -l debug_log_path
```

where *license_file_path* is the full path to the license file and *debug_log_path* is the full path to the debug log file.

Note: On VMS and Netware systems, there is no `lmgrd` and the vendor daemon is run directly.

3.1 Specifying Location of the License File

Most software vendors recommend a specific location for your license file. If you are running the application on multiple nodes, you have these options for making your license available on all the machines:

- Place the license file in a partition which is available (via NFS on UNIX systems) to all nodes in the network that need the license file.
- Copy the license file to all of the nodes where it is needed.

Specifying Location of the License File

- Set `LM_LICENSE_FILE` to `port@host`, where `host` and `port` come from the `SERVER` line in the license file. With v6+, you can use `@host`, if the license file `SERVER` line uses a default port or specifies a port in the default port range (27000-27009).
- On Windows (v6+), if the application can't find the license, the user is presented with a dialog box that asks for the license location or the name of the system running the license server or that allows the user to type in the license directly.

Since the vendor daemon keeps track of license usage, and since the license file contains encrypted data to protect it against modification, you may move and copy the license file as much as necessary.

For counted licenses, no matter which option you choose, you must first install `lmgrd` and the vendor daemon.

With a `FLEXlm v6+` vendor daemon and `lmgrd`, the license path can be a list of files, separated by colons on UNIX or semi-colons on Windows. If there is a directory in this list, all files named `*.lic` in that directory are used.

Note: You can only start `lmgrd` on the server node specified in the license file.

Note: If you are running redundant servers, you should have separate copies of the license file (as well as the binaries for `lmgrd` and the vendor daemons) on *each* server node. If you do not do this, you lose all the advantages of having redundant servers, since the file server holding these files becomes a single point of failure.

3.1.1 Starting the License Server at System Startup

If any licenses in the license file are counted (license count > 0), then the license server must be started before the product can be used.

UNIX

To start the license manager daemon (`lmgrd`), execute a command similar to the following.

If you are running in the C shell:

```
lmgrd_path -c license_file_path -l debug_log_path &
```

If you are using either the Korn or Bourne shell:

```
nohup lmgrd_path -c license_file_path -l debug_log_path 2>&1 &
```

On UNIX, edit the appropriate boot script, which may be `/etc/rc.boot`, `/etc/rc.local`, `/etc/rc2.d/Sxxx`, `/sbin/rc2.d/Sxxxx`, etc. Remember that these scripts are run in `/bin/sh`, so do not use the `cs`h `>&` redirection syntax.

Each UNIX operating system can have some quirks in doing this, but the following script has been successfully tested for HP700 systems. See the notes following for a full explanation.

```
/bin/su daniel -c 'echo starting lmgrd > \
/home/flexlm/v5.12/hp700_u9/boot.log'
```

```
/bin/nohup /bin/su daniel -c 'umask 022; \
/home/flexlm/v5.12/hp700_u9/lmgrd -c \
/home/flexlm/v5.12/hp700_u9/license.dat >> \
/home/flexlm/v5.12/hp700_u9/boot.log'
```

```
/bin/su daniel -c 'echo sleep 5 >> \
/home/flexlm/v5.12/hp700_u9/boot.log'
```

```
/bin/sleep 5
```

```
/bin/su daniel -c 'echo lmdiag >>\
/home/flexlm/v5.12/hp700_u9/boot.log'
```

```
/bin/su daniel -c '/home/flexlm/v5.12/hp700_u9/lmdiag -n -c\
/home/flexlm/v5.12/hp700_u9/license.dat >> \
/home/flexlm/v5.12/hp700_u9/boot.log'
```

```
/bin/su daniel -c 'echo exiting >>\
/home/flexlm/v5.12/hp700_u9/boot.log'
```

Please note the following about how this script was written:

- All paths are specified in full, because no paths can be assumed at boot time.
- Because no paths are assumed, the vendor daemon must be in the same directory as `lmgrd`, or the `DAEMON` lines must be edited to include the full path to the vendor daemon.

Specifying Location of the License File

- The `su` command is used to run `lmgrd` as a non-root user, “daniel.” We recommend that `lmgrd` not be run as “root,” since it can be a security risk to run any program as “root” that does not require root permissions, and `lmgrd` does not require root permissions.
- Daniel has a `csch` login, so all commands executed as “daniel” must be in `csch` syntax. All commands not executed as “daniel” must be in `/bin/sh` syntax, since that is what is used by the boot scripts.
- The use of `nohup` and `sleep` are required on some operating systems, notably HP-UX and Digital UNIX, for obscure technical reasons. These are not needed on Solaris and some other operating systems, but are safe to use on all.
- `lmdiag` is used as a diagnostic tool to verify that the server is running and serving licenses.

Note: On IBM RS6000 systems, `/etc/rc` cannot be used, because TCP/IP is not installed when this script is run. Instead, `/etc/inittab` must be used. Add a line like this to `/etc/inittab` after the lines which start networking:

```
rclocal:2:wait:/etc/rc.local > /dev/console 2>&l
```

Note: This will not start the daemon until you reboot your license server machine.

WINDOWS

From LMTOOLS, start `lmgrd`. You can optionally indicate that this should be started at system startup.

3.1.2 Setting the Path with an Environment Variable

Most applications specify a location where they expect to find the license file. Many will automatically install the license. You should rarely, if ever, be required to specify where the license file is located with an environment variable. However, you can change the license location with `LM_LICENSE_FILE`, or if a location is not set by the application, you can set one.

Use the environment variable `LM_LICENSE_FILE` to set the location of the license file. For example in the C shell:

```
setenv LM_LICENSE_FILE license_file_path
```

In the Korn and Bourne shells:

```
LM_LICENSE_FILE=license_file_path
export LM_LICENSE_FILE
```

On Windows 95, add the following line to C:\autoexec.bat:

```
SET LM_LICENSE_FILE=license_file_path
```

On Windows NT, use the System Control Panel to change the global environment, adding LM_LICENSE_FILE to *license_file_path*, where *license_file_path* is the full path to the license file. This can also be a *port@host* setting, where *port* and *host* are the port number and host name from the SERVER line in the license file. v6+ applications can use simply *@host*, if the server uses a default port number.

In FLEXlm v6+, applications will accept an environment variable (or Windows Registry) named *VENDOR_LICENSE_FILE*, where *VENDOR* is the vendor daemon name, e.g., *GSI_LICENSE_FILE*.

With *lmgrd* and *lmutil* (*lmstat*, *lmdown*, etc.), the *-c* option overrides the setting of the LM_LICENSE_FILE environment variable. See Section 4.1.3, “Using Separate License Files on the Same Server Node,” for more information about LM_LICENSE_FILE.

Note: Some applications do not recognize the LM_LICENSE_FILE environment variable.

See also Appendix C, “FLEXlm Environment Variables.”

3.2 License File Format

License files usually begin with a SERVER line (or three lines for redundant servers) followed by one or more DAEMON lines, followed by one or more FEATURE or INCREMENT lines. In some cases the license file requires no SERVER line and no DAEMON line. See Section 5.4, “Counted vs. Uncounted Licenses,” for more information. Since FLEXlm v6.0, the DAEMON line can be called VENDOR. Wherever DAEMON appears, VENDOR can be used, if the *lmgrd* and vendor daemon are both \geq FLEXlm v6.0.

You can modify these data items in the license file:

- Node names on the SERVER line(s)
- Port numbers on the SERVER line(s)

- Paths on the DAEMON line(s)
- Options file paths on the DAEMON line(s)
- Optional port numbers on the DAEMON line(s) (for firewall support only)
- USE_SERVER line (FLEXlm v5+ only)
- Values in *keyword=value* pairs on FEATURE lines, if *keyword* is all lowercase

Long lines normally use the “\” line-continuation character to break up long lines (though this is not required with v7+ applications). FLEXlm v2 did not support the line-continuation character, although this rarely matters since optional attributes weren’t support then either.

Note: Everything else is used to compute the license key or signature, and should be entered exactly as supplied by your software vendor. All data in the license file is case sensitive, unless otherwise indicated.

3.2.1 SERVER Lines

The SERVER line specifies the node name and hostid of the license server and the port number of the license manager daemon (`lmgrd`). Normally a license file has one SERVER line. Three SERVER lines mean that you are using redundant servers. The absence of a SERVER line means that every FEATURE or INCREMENT line in the license file is uncounted. For more information about uncounted features, see Section 3.2.4, “FEATURE or INCREMENT Lines.” License administrators do not have the option of deleting SERVER lines from a license file because the hostids from the SERVER lines are computed into the license key or signature on every FEATURE and INCREMENT line. For more information about redundant servers, see Chapter 5, “Selecting Server Nodes.”

The format of the SERVER line is:

```
SERVER host hostid [port]
```

where:

<i>host</i>	The system host name or IP address. String returned by the UNIX <code>hostname</code> or <code>uname -n</code> command. On NT, <code>ipconfig /all</code> ; on Windows 95, <code>winipcfg /all</code> return the host name. If the application uses FLEXlm v5 or higher, this can be an IP address (in <code>###.###.###.###</code> format).
<i>hostid</i>	Usually the string returned by the <code>lmhostid</code> command. This can only be changed by your software supplier.
<i>port</i>	TCP port number to use. A valid number is any unused port number between 0 and 64000. On UNIX, choose a port >1024, since those <1024 are privileged port numbers. The port number is optional if <code>lmgrd</code> , the vendor daemon, and the application are v6+ (if no port number is specified, one of the default ports in the range of 27000 and 27009 will be used).

Example:

```
SERVER enterprise 0122345 21987
```

3.2.2 DAEMON (or VENDOR) Lines

The DAEMON line specifies the daemon name and path. `lmgrd` uses this line to start the vendor daemon, and the vendor daemon reads it to find its options file. The format of the DAEMON line is shown below.

Note: Since FLEXlm v6.0, the DAEMON line can be called VENDOR. VENDOR can be used if the `lmgrd` and vendor daemon are both at least FLEXlm v6.0.

License File Format

```
{DAEMON|VENDOR} vendor [vendor_daemon_path]\  
  [[options=]options_file_path] [[port=]port]
```

where:

<i>vendor</i>	Name of the vendor daemon used to serve some feature(s) in the file. This name cannot be changed by the administrator.
<i>vendor_daemon_path</i>	Path to the executable for this daemon. Generally the license administrator is free to install the daemon in any directory. (It is recommended, however, that it be installed in a local directory on the license server node.) If the vendor daemon is v6+, this path is optional. If left out, lmgrd will look for the vendor daemon binary in the current directory, the PATH list, or in the directory where lmgrd is located. If the vendor daemon path is blank, then the options= and port= strings are required if options or port number are specified.
<i>options_file_path</i>	Full path to the end-user options file for this daemon. (See Chapter 6, “The Options File.”) FLEXlm does not require an options file. The keyword options= requires a v5+ vendor daemon. If the vendor daemon is v6+, the options file need not be specified on this line. If it is called vendor.opt (where vendor is the vendor daemon name) and located in the same directory as the license file, the vendor daemon will automatically find and use it.

port Vendor daemon port number. This requires a v5+ lmgrd.
 Note: This is for firewall support only and is otherwise not recommended. If a port number is specified on the DAEMON line, there is a delay restarting the vendor daemon until all the clients have closed their connections to the vendor daemon.

v6.0:

```
VENDOR sampled
```

pre-v6.0:

```
DAEMON sampled /etc/sampled \  

  /a/b/sampled/licenses/sampled.opt
```

3.2.3 USE_SERVER Line (v5+ only)

USE_SERVER takes no arguments and has no impact on the server. When the application sees USE_SERVER, it ignores everything in the license file except preceding SERVER lines, and the checkout validation occurs at the vendor daemon. USE_SERVER is recommended since it improves performance when a license server is used. For uncounted features, USE_SERVER can be used to force logging of usage by the daemons.

3.2.4 FEATURE or INCREMENT Lines

A FEATURE line describes the license to use a product. An INCREMENT line can be used in place of a FEATURE line, as well as to incrementally add licenses to a prior FEATURE or INCREMENT line in the license file.

Only the first FEATURE line for a given feature will be processed by the vendor daemon. If you want to have additional copies of the same feature (for example, to have multiple node-locked, counted features), then you must use multiple INCREMENT lines. INCREMENT lines form license groups based on the feature name, version, and node-lock hostid. If the feature name, version, and node-lock hostid (and optionally, the vendor string, if the vendor specified this) match a prior INCREMENT or FEATURE line, the new number of licenses is added to the old number. If any of the three do not match, a new group of licenses is created in the vendor daemon, and this group (called a *license pool*) is counted independently from others with the same feature name.

INCREMENT is not available for pre-v2.61 FLEX*lm* clients or servers. A FEATURE line does not give an additional number of licenses, whereas an INCREMENT line always gives an additional number of licenses.

Note: There is a rarely used option in FLEX*lm* which causes FEATURE lines to function as INCREMENT lines. This option is called `ls_use_all_feature_lines`. You will have to ask your vendor if they use this option. If they do, then all FEATURE lines behave exactly as INCREMENT lines.

Note: A FEATURE line placed after another FEATURE or INCREMENT line will be ignored (unless `ls_use_all_feature_lines` is set).

The format for the FEATURE line changed in FLEX*lm* v3.0 and again in FLEX*lm* v6.0. The older formats are understood by new clients and servers, but the new formats are more flexible.

v2 format:

```
{FEATURE|INCREMENT} feature vendor \
feat_version exp_date num_lic key \
"vendor_str" [feat_hostid]
```

v3–v7.0 format:

```
{FEATURE|INCREMENT} feature vendor feat_version \
exp_date num_lic key [HOSTID=feat_hostid] \
[VENDOR_STRING="vendor_str"] [vendor_info="..."] \
[dist_info="..."] [user_info="..."] [asset_info="..."] \
[ISSUER="..."] [NOTICE="..."] [ck=nnn] [OVERDRAFT=nnn] \
[DUP_GROUP=NONE|SITE|[UHDV]]
```

v7.1+ format:

```
{FEATURE|INCREMENT} feature vendor feat_version \
exp_date num_lic [HOSTID=feat_hostid] \
[VENDOR_STRING="vendor_str"] [vendor_info="..."] \
[dist_info="..."] [user_info="..."] [asset_info="..."] \
[ISSUER="..."] [NOTICE="..."] [ck=nnn] [OVERDRAFT=nnn] \
[DUP_GROUP=NONE|SITE|[UHDV]] SIGN=sign
```

Note: Nothing in a FEATURE/INCREMENT line is editable, except for values in `keyword=value` pairs where `keyword` is all lowercase.

where:

<i>feature</i>	Name given to the feature by the vendor.
<i>vendor</i>	Name of the vendor daemon; also found in the DAEMON line. The specified daemon serves this feature.
<i>feat_version</i>	Version of this feature that is supported by this license.
<i>exp_date</i>	Expiration date of license, e.g., 7-may-1996. Note: If the year is 0 (or 00, 000, 0000) then the license never expires. Dates before 2000 can be two- or four-digit years. After 2000 they must be four-digit years. The expiration date is fully year-2000 compliant. FLEXlm v6 (or later) applications only: the keyword “permanent” can be used instead of the date 1-jan-0.
<i>num_lic</i>	Number of concurrent licenses for this feature. If the number of licenses is set to 0, the licenses for this feature are uncounted and no <code>lmgrd</code> is required but a <code>hostid</code> on the FEATURE line is required. See Section 5.4, “Counted vs. Uncounted Licenses.” FLEXlm v6 (or later) applications only: the keyword “uncounted” can be used instead of a license count of 0.
<i>key</i>	License key to authenticate this FEATURE line. Two identical-looking FEATURE or INCREMENT lines may have different license keys if the start dates are different.
<code>SIGN=</code> <i>sign</i>	SIGN= signature to authenticate this FEATURE line. (v7.1+)

The following fields are all optional (except for `vendor_str` in the v2 format). For optional fields of the `keyword=value` syntax, if the `keyword` is lowercase, it can be modified and the license will remain valid.

<code>vendor_str</code>	Vendor-defined string, enclosed in double quotes. This string can contain any characters except a quote. Required field in the v2 format.
<code>feat_hostid</code>	String returned by <code>lmhostid</code> . Used only if the feature is to be bound to a particular host, whether its use is counted or not. Numeric hostids are case insensitive. See Appendix A, "Hostids for FLEXlm-Supported Machines," for more information.
<code>DUP_GROUP=...</code>	<p>Duplicate grouping parameter can be specified in the license in FLEXlm v4.0 and later. The syntax is:</p> <pre>DUP_GROUP=NONE SITE [UHDV] U = DUP_USER H = DUP_HOST D = DUP_DISPLAY V = DUP_VENDOR_DEF</pre> <p>Any combination of UHDV is allowed, and the DUP_MASK is the OR of the combination. For example, DUP_GROUP=UHD means the duplicate grouping is (DUP_USER DUP_HOST DUP_DISPLAY), so for a user on the same host and display, additional uses of a feature do not consume additional licenses.</p>
<code>HOSTID=feat_hostid</code>	Same as <code>feat_hostid</code> above, but in the <code>keyword=value</code> pair syntax (FLEXlm v3.0 and later).

HOST_BASED[= <i>n</i>]	Host names must be specified in INCLUDE statements in the end-user options file, and the number of hosts is limited to <i>num_lic</i> , or the number specified in = <i>n</i> .
ISSUED= <i>dd-mmm-yyyy</i>	Date issued.
ISSUER="..."	Issuer of the license.
NOTICE="..."	A field for intellectual property notices.
OVERDRAFT= <i>n</i>	FLEXlm v4.0 and later. The overdraft policy allows your vendor to specify a number of additional licenses which users will be allowed to use, in addition to the licenses they have purchased. This allows your users to not be denied service when in a “temporary overdraft” state. Usage above the license limit will be reported by the SAMreport reporting tool.
PLATFORMS="..."	Usage is limited to the listed platforms. (v5.11+ only).
SN= <i>serial_num</i>	Serial number, used to identify FEATURE or INCREMENT lines.
START= <i>dd-mmm-yyyy</i>	Start date (FLEXlm v6 or later only).
SUPERSEDE= <i>"f1 f2 ..."</i>	If this appears, all licenses issued before the date specified in ISSUED= are <i>superseded</i> by this line and become ineffective.
USER_BASED[= <i>n</i>]	Users must be specified in INCLUDE statements in the end-user options file, and the number of users are limited to <i>num_lic</i> , or the number specified in = <i>n</i> .
VENDOR_STRING= <i>"..."</i>	Same as “ <i>vendor_str</i> ” above, but in <i>keyword=value</i> pair syntax.

The following attributes can be changed or deleted by end users. This is indicated by a lowercase *keyword*.

<code>asset_info=</code> <code>"..."</code>	Additional information provided by the license administrator for asset management.
<code>ck=nnn</code>	A checksum, useful with the <code>lmcksum</code> utility, which will verify that the license has been entered correctly by the end user.
<code>dist_info=</code> <code>"..."</code>	Additional information provided by the software distributor.
<code>user_info=</code> <code>"..."</code>	Additional information provided by the license administrator.
<code>vendor_info=</code> <code>"..."</code>	Additional information provided by the software vendor.

Examples:

```
FEATURE xyz_app xyzd 2.300 31-dec-2005 20 123456789012 "xyz"  
INCREMENT f1 xyzd 1.000 1-jan-0 5 901234567890 \  
    HOSTID=INTERNET=195.186.*.* NOTICE="Licensed to XYZ corp"
```

3.2.5 PACKAGE Lines

The purpose of the PACKAGE line is to support two different licensing needs:

- To license a product SUITE, or
- To provide a more efficient way of distributing a license file that has a large number of features, which largely share the same FEATURE line arguments.

A PACKAGE line, by itself, does not license anything—it requires a matching FEATURE/INCREMENT line to license the whole package. A PACKAGE line can be shipped by your software vendor with a product, independent of any licenses. Later, when you purchase a license for that package, one or more corresponding FEATURE/INCREMENT lines will enable the PACKAGE line.

Example:

```
PACKAGE package vendor pkg_version COMPONENTS=pkg_list \  
[OPTIONS=SUITE] SIGN=pkg_sign
```

where:

<i>package</i>	Name of the package. The corresponding FEATURE/INCREMENT line must have the same name.
<i>vendor</i>	Name of the vendor daemon that supports this package.
<i>pkg_version</i>	Version of the package. If specified, the enabling FEATURE/INCREMENT line must have the same version.
<i>pkg_sign</i>	License key or SIGN= signature.
<i>pkg_list</i>	List of package components. The format is: <i>feature[:version[:num_lic]]</i> Packages must consist of at least one component. Version and count are optional, and if left out, their values come from the corresponding FEATURE/INCREMENT line. <i>num_lic</i> is only legal if OPTIONS=SUITE is not set—in this case the resulting number of licenses will be <i>num_lic</i> on the COMPONENTS line multiplied by the number of licenses in the FEATURE/INCREMENT line. Examples: COMPONENTS="comp1 comp2 comp3 comp4" COMPONENTS="comp1:1.5 comp2 comp3:2.0:4"

`OPTIONS=SUITE` This is what distinguishes a package suite from a package used to ease distribution. With `OPTIONS=SUITE`, the corresponding feature of the same name as the package is checked out in addition to the component feature being checked out. If `OPTIONS=SUITE` is not set, then the corresponding feature of the same name as the package is removed once the package is enabled; is not checked out when a component feature is checked out.

Examples:

```
PACKAGE suite xyzd 1.0 3B24B2F508CB \  
  COMPONENTS="comp1 comp2" OPTIONS=SUITE  
FEATURE suite xyzd 1.0 1-jan-0 5 4193E6ABCCCB
```

This is a typical `OPTIONS=SUITE` example. There are two features, “comp1” and “comp2,” which are each version 1.0, each with five non-expiring licenses available. When “comp1” or “comp2” is checked out, “suite” will also be checked out.

```
PACKAGE suite xyzd 1.0 2CBF44FCB9C1 \  
  COMPONENTS="c1:1.5:2 c2:3.0:4"  
FEATURE suite xyzd 1.0 1-jan-2005 3 321E78A17EC1 SN=123
```

In this example, the component version overrides the feature version, and the number of licenses available for any component is the product of the three licenses for “suite” and the number of licenses for that component. The result is equivalent to:

```
FEATURE c1 xyzd 1.5 1-jan-2005 6 0D3AD5F26BEC SN=123  
FEATURE c2 xyzd 3.0 1-jan-2005 12 EB16C5AE61F0 SN=123
```

With *FLEXlm* v6 (or later) applications only the `PACKAGE` lines can be stored in a separate file which need never be edited.

3.2.6 UPGRADE Lines

```
UPGRADE feature vendor from_feat_version to_feat_version \
        exp_date num_lic [options ... ] SIGN=sign
```

All the data is the same as for a FEATURE or INCREMENT line, with the addition of the *from_feat_version* field. An UPGRADE line removes up to the number of licenses specified from any old version (\geq *from_feat_version*) and creates a new version with that same number of licenses.

For example, the two lines:

```
INCREMENT f1 xyzd 1.000 1-jan-2005 5 SIGN=9BFAC0316462
UPGRADE f1 xyzd 1.000 2.000 1-jan-2005 2 SIGN=1B9A308CC0F7
```

would result in three licenses of v1.0 of “f1” and two licenses of v2.0 of “f1.”

An UPGRADE line will operate on the closest preceding FEATURE or INCREMENT line with a version number that is \geq *from_feat_version*, and $<$ *to_feat_version*.

Note that UPGRADE lines do not work for node-locked, uncounted licenses before v6.

3.3 Sample License File

This is an example of a license file for a single vendor with two features.

```
SERVER excellent_server 17007ea8 1700
DAEMON xyzd /etc/xyzd
FEATURE xyz_app1 xyzd 1.000 01-jan-2005 10 1EF890030EAB
FEATURE xyz_app2 xyzd 1.000 01-jan-2005 10 084561FE98B3
```

The license file above would allow the license server “excellent_server” with the hostid “17007ea8” to serve ten floating licenses for “xyz_app1” and “xyz_app2” to any user on the network.

3.4 Types of License Files

License files are created by the software vendor. License files can specify floating (concurrent) usage, node-locked (both counted and uncounted), and any combination of floating, counted, and uncounted.

3.4.1 Floating (Concurrent) Licenses

A *floating license* means anyone on the network can use the licensed software, up to the limit specified in the license file (also referred to as *concurrent usage* or *network licensing*). Floating licenses have no hostids on the individual FEATURE lines. Floating licenses requires an `lmgrd` and a vendor daemon to be running to count the concurrent usage of the licenses.

An example of a license file that provides floating licenses is:

```
SERVER lulu 17001234 1700
DAEMON xyzd /etc/xyzd
FEATURE f1 xyzd 1.00 1-jan-2005 2 key1 ""
FEATURE f2 xyzd 1.00 1-jan-2005 6 key2 ""
FEATURE f3 xyzd 1.00 1-jan-2005 1 key3 ""
```

This license file specifies that two licenses for feature “f1,” six licenses for feature “f2,” and one license for feature “f3” are available anywhere on the network that can access the license server “lulu.”

3.4.2 Node-Locked Licenses

Node-locking means the licensed software can only be used on one node. A node-locked license has a hostid on any FEATURE line that is node-locked to a particular host. There are two types of node-locked licenses; uncounted and counted.

If the number of licenses is set to 0, then the license is uncounted and unlimited use is permitted on the specified node. This configuration does not require an `lmgrd` or a vendor daemon because it is not going to count the concurrent usage of the features.

The following license file allows unlimited usage of feature “f1” on the nodes with hostids of “12001234” and “1700ab12”:

```
FEATURE f1 xyzd 1.000 1-jan-2005 0 key1 "" 12001234
FEATURE f1 xyzd 1.000 1-jan-2005 0 key2 "" 1700ab12
```

Alternately, in `FLEXlm v5.0` or later, these two FEATURE lines could have been issued by your software vendor with a *hostid list*:

```
FEATURE f1 xyzd 1.000 1-jan-2005 0 key HOSTID="12001234 1700ab12"
```

If these were the only FEATURE lines in this license file, no `lmgrd` daemon would be necessary and you should not start one.

The following license file allows three licenses for feature “f1” to be run, but only on the node with hostid “1300ab43.” In this case, the daemons should be run on the same node that runs the software, since there is no reason to run the daemons on another node.

```
SERVER lulu 1300ab43 1700
DAEMON xyzd /etc/xyzd
FEATURE f1 xyzd 1.00 1-jan-2005 3 key HOSTID=1300ab43
```

3.4.3 Mixed Node-Locked and Floating Licenses

Uncounted node-locked and concurrent usage licenses can be mixed in the same license file.

The following license file allows unlimited use of feature “f1” on nodes “17001111” and “17002222,” while allowing two other licenses for feature “f1” to be used anywhere else on the network:

```
SERVER lulu 17001234 1700
DAEMON xyzd C:\flexlm\xyzd.exe
FEATURE f1 xyzd 1.00 1-jan-2005 0 key1 HOSTID=17001111
FEATURE f1 xyzd 1.00 1-jan-2005 0 key2 HOSTID=17002222
FEATURE f1 xyzd 1.00 1-jan-2005 2 key3
```

This configuration requires an lmgrd and a vendor daemon because the concurrent usage of the two licenses on the third FEATURE line is counted.

3.5 Decimal Format

The decimal format was introduced in v6. Users with older products can still use the decimal format, but they will require a copy of the lminstall command (which is part of lmutil). The lminstall utility allows the user to type in a decimal line, which is then converted to the readable format, and saved in the specified location. The mixed node-locked and floating example above looks as follows in decimal format:

```
xyzd-f1-01761-55296-37046-04544-00017-06551-18072-57346-18754-136
xyzd-f1-01761-55296-37046-08896-00034-235
xyzd-f1-00481-55296-17590-2
```

A simple demo license in readable format:

```
FEATURE f1 xyzd 1.00 1-jan-2005 0 key1 HOSTID=DEMO
```

converted to decimal:

```
xyzd-f1-00737-55296-1825
```

Note that by default `lminstall` converts to v6 format. It can convert to a format compatible with older versions by using `lminstall -overfmt 2` (or 3, 4, 5, 5.1, 6, 7, or 7.1, depending on the *FLEXlm* version).

3.6 License File Order

In some cases, the ordering of lines in a license file can be crucial. Version 7+ vendor daemons and clients automatically internally sort the lines so that in most cases the optimal result is achieved. For earlier versions of *FLEXlm*, note the following suggestions, which are all based on the fact the checkouts are attempted on lines in the order they appear in the license file:

1. **Place FEATURE lines before INCREMENT lines for the same feature.**

The rule regarding FEATURE lines is that only the first counted FEATURE line is observed by the license server, and that if there is a FEATURE line and INCREMENT lines, the FEATURE line must appear first. (A few large, older *FLEXlm*-licensed companies have FEATURE lines that behave identically to INCREMENT lines, and only the rules applying to INCREMENT apply to them.)

2. **Where multiple counted FEATURE lines exist for the same feature, make sure the desired FEATURE line appears first.**

All but the first is ignored.

3. **Place node-locked, uncounted lines before floating lines for the same FEATURE.**

Otherwise, the floating license may be consumed when a node-locked would have been used, resulting in denial for other users.

4. **The placement of a USE_SERVER line affects behavior.**

A `USE_SERVER` line is recommended. Normally, the `USE_SERVER` line is placed immediately after the `SERVER` line. However, if there are uncounted licenses which you don't want to fail if the server is unavailable, these should be placed at the top of the file, with the `USE_SERVER` line following them. This only works, however, if each user that needs the uncounted license has direct access to a current copy of the file. The advantage to placing `USE_SERVER` right after the `SERVER` line is users don't need up-to-date copies of the license file.

Multiple License Files

Since more than 2000 vendors have chosen FLEXlm as their license manager, chances are good that you will have to administer FLEXlm licenses from more than one vendor or multiple products from the same vendor.

4.1 Overview of Combining License Files

When you are running FLEXlm-licensed products from multiple vendors, you may need to take steps to prevent licensing conflicts during installation. There are three ways you can accomplish this:

- Multiple license server nodes, each running one `lmgrd` and one license file
- One license server node running one `lmgrd` and several license files
- One license server node running multiple `lmgrds` and multiple license files

Note that before v6, each `lmgrd` could read only a single license file. In the first option mentioned above, you will have more license servers to monitor; in the third option you have only one server but multiple `lmgrds` to administer.

If all applications and vendor daemons are FLEXlm v6+, `lmgrd` can process multiple license files, even when the hostids in each license file are different, so long as they refer to the same node. For example, on UNIX:

```
lmgrd -c license_file_path_1:license_file_path_2 ...
```

Your product's license file(s) define the license server(s) by host name and hostid in the `SERVER` line(s) in the license file. If the license files for two or more products contain identical hostids on the `SERVER` line(s), then these files can be combined. If the license files for two products contain different hostids on a `SERVER` line, then the license servers for those products will be running on different nodes and the license files cannot be combined.

If you have two or more products whose license servers run on the same node (as specified by the `SERVER` lines in the license files), you may be able to combine the license files into a single license file. If the `SERVER` lines in those

files have identical hostids, then you can combine the files into a single file. If the SERVER lines have different hostids, then you must keep the license files separate.

More precisely, you can combine two license files under the following conditions:

1. The number of SERVER lines in each file is the same.
2. The hostid field of each SERVER line in one file exactly matches the hostid field of each SERVER line in the other file.

Some possible reasons license files may not be compatible are:

- License files are set up to run on different server nodes, so hostids are different.
- One file is set up for single server (has only one SERVER line), the other is set up for redundant servers (has multiple SERVER lines).
- One vendor uses a custom hostid algorithm, so the hostids on the SERVER lines are different, even though the files are for the same machine.

If your license files are compatible as described above, then you have the option of combining license files and running a single `lmgrd`, as described below in Section 4.1.1, “Combining License Files from Multiple Vendors.” If the license files are not compatible, then you must keep the license files separate and run separate copies of `lmgrd` for each license file, as described in Section 4.1.3, “Using Separate License Files on the Same Server Node.”

Note that you are not required to combine compatible license files; you always have the option of running separate `lmgrds`, and there is virtually no performance or system-load penalty for running separate `lmgrd` processes.

4.1.1 Combining License Files from Multiple Vendors

If your license files are compatible, you can combine them with any text editor. To combine license files, read all of the compatible license files into one file, then edit out the extra SERVER lines so that only one set of SERVER lines remains. Write out this data, and you have your combined license file. If you combine license files from multiple vendors, it is a good idea to keep a copy of the combined license file in each vendor’s default license file location. This way, users can avoid having to set `LM_LICENSE_FILE`, because each package finds its license information in the default place. On UNIX, you can do this with a symbolic link from each default location to the location of the combined license file.

4.1.2 FLEXlm Version Component Compatibility

When you combine license files for two different FLEXlm-licensed products, it may be the case that those products do not use the same version of FLEXlm. FLEXlm is designed to handle this situation. There are two basic compatibility rules for FLEXlm:

- A newer lmgrd can be used with an older vendor daemon, but a newer vendor daemon might not work properly with an older lmgrd.
- A newer vendor daemon (or lmgrd) can be used with an older client program, but a newer client program might not work properly with an older vendor daemon.

From these two compatibility rules come the simple rules for selecting which version of administration tools to use:

1. Always use the newest version of lmgrd and the newest version of each vendor daemon.
2. Use the newest FLEXlm utilities.

For specific application programs, you can use either the new or the old version (of course, the vendor daemon for that application must be at least as new as the application itself). See also Section G.1, “Version Compatibility and Components.”

4.1.3 Using Separate License Files on the Same Server Node

You must run a separate copy of lmgrd for each license file. When you run multiple copies of lmgrd, there are two details to remember:

1. The port number on the SERVER line of each license file must be unique. You can use a standard text editor to change the port number in each license file so that they are all different.
2. You must make sure that you are using a compatible version of lmgrd when you start it up for a particular license file. This can be done by using an explicit path to lmgrd.

When running client programs (such as a licensed application), you can set the LM_LICENSE_FILE environment variable to point to multiple license files. For example, you may have a license file from vendor “ABC” and a license file from vendor “XYZ” with incompatible servers. You can place the license file from vendor “ABC” into:

```
/usr/flexlm/abc.lic
```

and the license file from vendor “XYZ” into:

```
/usr/flexlm/xyz.lic
```


Using LM_LICENSE_FILE License File List

then set the `LM_LICENSE_FILE` environment variable to point to both of them. Each name in `LM_LICENSE_FILE` should be separated by a colon (“:”) on UNIX systems, a semicolon (“;”) on Windows and Windows/NT systems (in *FLEXlm* v4.1, a comma was used on Windows and NT), and a space (“ ”) on VMS systems.

In the C shell:

```
setenv LM_LICENSE_FILE /usr/flexlm/abc.lic:/usr/flexlm/xyz.lic
```

In the Korn and Bourne shells:

```
LM_LICENSE_FILE=/usr/flexlm/abc.lic:/usr/flexlm/xyz.lic
export LM_LICENSE_FILE
```

4.2 Using LM_LICENSE_FILE License File List

If products use different license server nodes, each set of license servers requires separate license files. (When multiple software vendors use the same set of license server nodes, the technique described above in Section 4.1, “Overview of Combining License Files,” can be used to combine license files.) The resulting (multiple) license files can be installed in convenient locations. On UNIX you would set the `LM_LICENSE_FILE` environment variable as follows:

```
setenv LM_LICENSE_FILE lfpath1:lfpath2:...
```

where *lfpath1* is the path to the first license file, *lfpath2* is the path to the second license file, etc.

Note: Use a colon (“:”) to separate the license file names on UNIX, on Windows and Windows/NT use a semicolon (“;”), and on VMS use a space (“ ”).

Each application queries each license file in the order it is listed in `LM_LICENSE_FILE`. If the license server serving the license file listed in *lfpath1* is unreachable, the other files listed in `LM_LICENSE_FILE` allow a user to obtain a license from another server. *lfpathn* can also be *port@host*, using the port number and host name from the `SERVER` line in the license file.

See also:

- Section 5.3.1, “Redundancy via License File List”
- Appendix C, “FLEXlm Environment Variables”
- Section 3.1.2, “Setting the Path with an Environment Variable”

Selecting Server Nodes

This chapter helps you decide which nodes to use as license server nodes.

5.1 Resources Used by the Server

This section discusses the resources used by the license server. When you select a server node, you may need to take into account the system limits on these resources. For small numbers of licenses (under about 100), most of these items should not be a problem on any workstation.

5.1.1 Sockets

When using TCP, a single vendor daemon can support as many users as the per-process system limit for file descriptors, which ranges from 256 on SunOS 4.x to 4000 on DEC Alpha. When no more file descriptors are available to a daemon, additional vendor daemons are spawned to allow for extra file descriptors, though this is not recommended. When using UDP, there is no limit to the number of end users per vendor daemon process, because they can share a single socket in the vendor daemon (UDP has other drawbacks, and TCP is preferred). If there are more than 250 concurrent clients from a SunOS vendor daemon, it may be a good idea to move the server to a different OS, since all other OSs support more file descriptors. If there are more than 1000 concurrent clients being supported by a single vendor daemon, then it's probably good to split the license file into more than one file, from different servers, to lighten the networking traffic (which will require the ISV to agree to issue new licenses). Clients can check out licenses from multiple servers using a license file list via the `LM_LICENSE_FILE` environment variable.

Each client connected to a license server uses one socket. The total number of sockets used by the license server programs is slightly larger than the total number of simultaneous clients.

On older SCO systems, the default number of sockets may be set fairly low; if you choose to run a server on such a machine, you may need to reconfigure your kernel to have more sockets.

The number of sockets available for Windows 95 clients is about 60. In general, NT is preferred for server systems, where there is no such limit, and the operating system is better designed for server processes.

5.1.2 CPU Time

For small numbers of clients, the license servers use very little CPU time. The servers might have only a few seconds of CPU time after many days.

For a large number of clients (who are each exchanging heartbeat messages with the server), or for high checkout/checkin activity levels (hundreds per second), the amount of CPU time consumed by the server may start to become significant, although, even here, CPU usage is normally not high. In this case, you may need to ensure that the server machine you select will have enough CPU cycles to spare.

Note: GLOBEtrouter Software has rarely encountered a situation where CPU cycles were an issue.

5.1.3 Disk Space

The only output files created by the license servers are the debug and report log files. The report log files are used to generate accurate usage reports by *SAMreport*. These log files contain one line for each checkout and one line for each checkin. If you have a lot of license activity, these log files will grow very large. You will need to consider where to put these files and how often to delete or prune them. The license administrator can opt not to log messages to the debug log file if disk space is at a premium. See Section 6.2.10, “NOLOG,” and Section 6.2.11, “REPORTLOG.”

Note that the log files should be local files on the server machine(s) to avoid networking dependencies.

SWITCHING OUTPUT OF THE DEBUG LOG FILE ON UNIX SYSTEMS

On UNIX, the debug log file output can be switched after the daemons are running. The technique to do this involves piping the stdout of `lmgrd` to a shell script that appends to the file for each line.

This is done as follows:

Instead of the “normal” startup:

```
lmgrd > LOG
```

Start `lmgrd` this way:

```
lmgrd | sh -c 'while read line; do echo "$line" >> LOG ; done'
```

With this startup method, the output file `LOG` can be renamed and a new log file will be created. You could even make `LOG` a symbolic link and change the value of the link to switch the log file.

5.1.4 Memory

The `FLEXlm` daemons use little memory. On SunOS, `lmgrd` uses approximately 160 KB and the vendor daemons use approximately 180 KB each, although memory usage increases in the vendor daemon with the size of the license file and the number of concurrent users.

5.1.5 Network Bandwidth

`FLEXlm` sends relatively small amounts of data across the network. Each transaction, such as a checkout or checkin, is typically satisfied with less than 1 KB of data transferred. This means that `FLEXlm` licensing can be effectively run over slow networks (such as dial-up SLIP lines) for small numbers of clients.

For a large number of clients (hundreds), each of which will be exchanging heartbeat messages with the vendor daemon, the network bandwidth used may start to become significant. In this case you should run client and server on the same local area network, which may require splitting licenses between two files for two servers. Users can use a license file list in the `LM_LICENSE_FILE` environment variable to have effective access to both servers.

In high-traffic networks, with `FLEXlm` clients older than v5, you may also want to avoid setting `LM_LICENSE_FILE` to a `port@host` address. Instead, the license administrator should place a copy of the license file in a file system local to the application. See Section 3.1, “Specifying Location of the License File.”

5.2 Remote Mounted Disks

GLOBEtrouter Software recommends that you do not use remote mounted disks when you run the license server. In other words, we recommend that `lmgrd`, the vendor daemons, the license file, and the debug and report log files are all on locally mounted disks. If any of these files is on a remote mounted

disk, you double the points of failure which could lead to a temporary loss of all of your licenses. When all files are mounted locally, the licenses will be available as long as the server machine is up; but when the files are on a different machine, then the loss of either the license server machine or the file server machine will cause the licenses to be unavailable.

5.3 Redundant Servers

If all the end-user data is on a single file server, then there is no need for redundant servers, and GLOBETrotter Software recommends the use of a single server node for the FLEX lm daemons. If the end user's data is split among two or more server nodes and work is still possible when one of these nodes goes down or off the network, then multiple server nodes can be employed. In all cases, an effort should be made to select stable systems as server nodes; in other words, do not pick systems that are frequently rebooted or shut down for one reason or another. Redundant license server nodes can be any supported server nodes—it is not required that they be the same architecture or operating system.

FLEX lm supports two methods of redundancy: redundancy via a license file list in the `LM_LICENSE_FILE` environment variable and a set of three redundant license servers.

With `LM_LICENSE_FILE` list redundancy, each one of a group of license servers serves a subset of the total licenses. The end user sets `LM_LICENSE_FILE` to a list of license files, where each license file refers to one of the license servers. The application then tries each server in the list, in order, until it succeeds or gets to the end of the list.

With three-server redundancy, if any two of the three license servers are up and running (two out of three license servers is referred to as a *quorum*), the system is functional and hands out its total complement of licenses.

See also Section 4.2, “Using `LM_LICENSE_FILE` License File List.”

5.3.1 Redundancy via License File List

This is best explained by example. If ten licenses are desired for both “f1” and “f2,” the ISV would issue two sets of licenses with a count of 5 for each of “f1” and “f2.” The server nodes (unlike three-server redundancy) can be physically distant.

The license files would look like:

License 1 for “chicago”

```
SERVER chicago 17007ea8 1700
DAEMON xyzd /etc/mydaemon
FEATURE f1 xyzd 1.000 01-jan-2005 5 26C7DD9C0186
FEATURE f2 xyzd 1.000 01-jan-2005 5 8CE46C57041D
```

License 2 for “tokyo”

```
SERVER tokyo 17007ea8 1700
DAEMON xyzd /etc/mydaemon
FEATURE f1 xyzd 1.000 01-jan-2005 5 16BE40E1D98D
FEATURE f2 xyzd 1.000 01-jan-2005 5 6DB6F3E402DF
```

The user in Chicago could set `LM_LICENSE_FILE` to:

```
1700@chicago:1700@tokyo
```

The user in Tokyo could set `LM_LICENSE_FILE` to:

```
1700@tokyo:1700@chicago
```

The application attempts the first server in the list, and if that fails for any reason, the second server is tried.

5.3.2 Three-Server Redundancy

These three-server redundant servers should have excellent communications and should be on the same subnet. Often this means that the three servers should be located physically close to each other. This form of redundancy requires that the servers exchange heartbeats periodically, and poor communications can cause poor performance. You should never configure redundant servers with slow communications or dial-up links.

Three-server redundancy does not provide load-balancing. Use `LM_LICENSE_FILE` list instead for this type of redundancy. This is because with three-server redundancy, only one of the three servers is “master,” capable of issuing licenses. Since all clients must contact the “master,” all clients must have reliable networking to a single node.

5.3.3 Comparing Three-Server to License File List

ARE THERE ANY DRAWBACKS TO USING THE LICENSE FILE LIST FOR REDUNDANCY?

Yes. By default, once a *license job* has successfully checked out a license from one host, all subsequent checkouts must be satisfied from the same host. If the application requires more than one license, this could result in a license denial when the license is available on another server. An application can bypass this

restriction if it is coded with the use of multiple *FLEXlm* license jobs. Only your application vendor can tell you if their application is programmed in this manner.

If the application supports license queueing, all licenses are only queued from the first host on the list.

Finally, if one server becomes unavailable, some licenses will be unavailable.

WHEN IS IT RECOMMENDED TO USE A LICENSE FILE LIST FOR REDUNDANCY RATHER THAN TRUE REDUNDANT SERVERS?

- When there's less system administration available to monitor license servers.
- When load-balancing is needed for clients located far apart, e.g., London and Tokyo. You can make servers available locally, with remote servers available as backup.
- License file list is more forgiving if you lose quorum.
- License file list is not limited to three servers (any number will work).
- Clients do not require reliable networking to a single node with license file list, so this is recommended where networking itself requires redundancy.

5.4 Counted vs. Uncounted Licenses

The license file determines whether a license server is needed. If all the *FEATURE* (or *INCREMENT*) lines have a license count of 0 (unlimited) or “uncounted” (*FLEXlm* v6 or later only), then no server is needed. This type of license is called uncounted. Alternatively, if any *FEATURE* lines have a non-zero license count, then a server is required to count those licenses. If a vendor wants to use *FLEXlm* without a server, they must issue uncounted licenses.

With *FLEXlm* v5 or later, the license server can serve uncounted licenses as well. This is done so that the report log file will include transactions for all license requests, which can then be reported on by *SAMreport*. To do this, include a *SERVER* line in the license file, and put the *USE_SERVER* line immediately after the *SERVER* line. The vendor daemon will serve the uncounted licenses, and the *USE_SERVER* line indicates to applications that they will be authorized by the server.

The Options File

The options file allows the license administrator to control various operating parameters of *FLEXlm*. Users can be identified by their user name, host name, display, IP address, or PROJECT (which is set with the `LM_PROJECT` environment variable).

Specifically, the license administrator can:

- Allow the use of features
- Deny the use of features
- Reserve licenses
- Control the amount of information logged about license usage
- Enable a report log file

Options files allow you, as the license administrator, to be as secure or open with licenses as you like.

Lines in the options file were limited to 200 characters prior to *FLEXlm* v3.0. In v3.0 and later, the line length is 2048 characters. *FLEXlm* v4.0 allows the “\” character as a continuation character in options file lines.

Identifying users by `LM_PROJECT` *in the options file* requires a v5+ application and v7+ vendor daemon.

6.1 Creating an Options File

To create an options file:

1. Use the appropriate options listed in Section 6.2, “Options File Syntax,” to create the options file using any text editor. You can put the options file anywhere; however, we recommend that the options file for vendor “XYZ” (whose vendor daemon is `xyzd`) be placed in:

UNIX: `/a/b/xyzd/licenses/xyzd.opt`

Windows: `C:\a\b\xyzd\licenses\xyzd.opt`

2. Add the path to the options file in the license file as the fourth field on the DAEMON line for the application’s vendor daemon. For example:

```
DAEMON xyzd /etc/xyzd /a/b/xyzd/licenses/xyzd.opt
```

would enable the `xyzd` vendor daemon to look at the specified options file. In `FLEXlm v5` or later, you can put `options=` before the path. In `FLEXlm v6` or later, adding the options path to the license file is optional. Instead, name the file `vendor.opt`, where `vendor` is the vendor daemon name, and place it in the same directory as the license used by `lmgrd`, and it will automatically be used at server startup.

6.2 Options File Syntax

Below is an overview of the options file syntax. See Section 6.5, “Options File Examples,” for examples and additional information.

Each line of the file controls one option. The options are:

EXCLUDE	Deny a user access to a feature.
EXCLUDEALL	Deny a user access to <i>all</i> features served by this vendor daemon.
GROUP	Define a group of users for use with any options.
HOST_GROUP	Define a group of hosts for use with any options (v4.0+).
INCLUDE	Allow a user to use a feature.
INCLUDEALL	Allow a user to use <i>all</i> features served by this vendor daemon.
LINGER	Cause licenses to be held by the vendor daemon for a period after the application checks them in or exits.
MAX	Limit usage for a particular feature/group—prioritizes usage among users.
MAX_OVERDRAFT	Limit overdraft usage to less than the amount specified in the license.

NOLOG	Turn off logging of certain items in the debug log file.
REPORTLOG	Specify that a report log file suitable for use by the <i>SAMreport</i> license usage reporting tool be written.
RESERVE	Reserve licenses for a user.
TIMEOUT	Specify idle timeout for a feature, returning it to the free pool for use by another user.
TIMEOUTALL	Set timeout on all features.

You can include comments in your options file by starting each comment line with a pound sign “#.” Everything in an options file is case sensitive. Be sure that user names and feature names, for example, are entered correctly.

FEATURE SPECIFICATION

Starting with *FLEXlm* v5, you can specify options for a particular line of a given feature name, as follows:

feature:keyword=value

For example:

`f1:VERSION=2.0`

You can specify a feature by any of the following fields:

VERSION=, HOSTID=, EXPDATE=, KEY=, SIGN=, VENDOR_STRING=, ISSUER=, NOTICE=, dist_info=, user_info=, asset_info=

In *FLEXlm* v5.11 or later, you can use a package name in place of a feature name, and the option will apply to all of the components in the package.

The following option keywords restrict who may use licenses or where licenses may be used: EXCLUDE, EXCLUDEALL, INCLUDE, INCLUDEALL, MAX, and RESERVE. These options take a *type* argument, which specifies whether the restriction is based on USER, HOST, DISPLAY, INTERNET, or PROJECT:

- USER—UNIX user name of the user executing the program
- HOST—machine where the application is executing

- **DISPLAY**—display where the application is displayed
DISPLAY is often confusing. Historically, the *FLEXlm* default on UNIX was `/dev/ttyxx` (which is always `/dev/tty` when an application is run in the background). Some newer applications now have it set to the X-Display name.
- **INTERNET**—IP address of the machine where the application is executing (wildcards can be used in the IP address)
- **PROJECT**—`LM_PROJECT` environment variable set by the user who is executing the program (requires v5+ client and v7+ vendor daemon)

On PCs, the **USER**, **HOST** and **DISPLAY** name are all set to the PC's host name.

The types listed above take a list of members, separated by spaces. For example:

```
EXCLUDE coolsoft USER joe barbara susan
```

Other valid types are **GROUP** and **HOST_GROUP**. These allow you to define a group of users or hosts on a separate line in the options file, then use those group names instead of an explicit list. For example:

```
GROUP stars joe barbara susan
EXCLUDE coolsoft GROUP stars
```

6.2.1 EXCLUDE

```
EXCLUDE feature[:keyword=value] type {list | group_name}
```

Excludes a list or pre-defined group of users, etc. from the list of who is allowed to use the feature. Excluded users will not be allowed to use the feature. **EXCLUDE** overrides **INCLUDE**.

<i>feature</i>	Name of the feature being affected.
<i>type</i>	One of USER , HOST , DISPLAY , INTERNET , PROJECT , GROUP , or HOST_GROUP .
<i>list</i>	List of <i>type</i> members to exclude.
<i>group_name</i>	Name of the group to exclude.

To exclude the user “hank” from the list of users able to use feature “f1”:

```
EXCLUDE f1 USER hank
```

6.2.2 EXCLUDEALL

```
EXCLUDEALL type {list | group_name}
```

Excludes a list or pre-defined group of users, etc. from the list of who is allowed to use all features served by this vendor daemon.

<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP.
<i>list</i>	List of <i>type</i> members to exclude.
<i>group_name</i>	Name of the group to exclude.

To exclude any user on the machine “chaos” from using all features served by this vendor daemon:

```
EXCLUDEALL HOST chaos
```

6.2.3 GROUP

```
GROUP group_name user_list
```

Defines a group of users for use in INCLUDE, INCLUDEALL, EXCLUDE, EXCLUDEALL, and RESERVE option lines.

<i>group_name</i>	Name of the group being defined.
<i>user_list</i>	List of user names in that group.

To define the group “Hackers” consisting of “bob,” “howard,” and “james”:

```
GROUP Hackers bob howard james
```

Note: In FLEXlm v3.0, multiple GROUP lines will add all the specified users into the group. Pre-v3.0 FLEXlm daemons do not allow multiple GROUP lines to concatenate—the last GROUP line would define the GROUP.

Note: In FLEXlm v4.0 or later, USER_GROUP is an alias for GROUP.

6.2.4 HOST_GROUP

```
HOST_GROUP group_name host_list
```

Defines a group of hosts for use in INCLUDE, INCLUDEALL, EXCLUDE, EXCLUDEALL, and RESERVE option lines. Multiple HOST_GROUP lines will add all the specified hosts into the group.

group_name Name of the group being defined.

host_list List of host names in that group.

To define the host group “Pacific” consisting of “tokyo,” “seattle,” and “auckland”:

```
HOST_GROUP Pacific tokyo seattle auckland
```

6.2.5 INCLUDE

```
INCLUDE feature[:keyword=value] type {list | group_name}
```

Includes a list or pre-defined group of users, etc. in the list of who is allowed to use the feature. Anyone not in an INCLUDE statement will not be allowed to use that feature. EXCLUDE overrides INCLUDE.

feature Name of the feature being affected.

type One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP.

list List of *type* members to include.

group_name Name of the group to include.

To include user “bob” in the list of users able to use feature “f1”:

```
INCLUDE f1 USER bob
```

Note: INCLUDE is required for USER_BASED or HOST_BASED features. The system administrator specifies which users are allowed to use the product, via INCLUDE, and the license limits the number of users that can be INCLUDED.

6.2.6 INCLUDEALL

```
INCLUDEALL type {list | group_name}
```

Includes a list or pre-defined group of users, etc. in the list of who is allowed to use all features served by this vendor daemon. Anyone not in an INCLUDEALL statement will not be allowed to use these features.

<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP.
<i>list</i>	List of <i>type</i> members to include.
<i>group_name</i>	Name of the group to include.

To allow the user “jane” to use all features served by this vendor daemon:

```
INCLUDEALL USER jane
```

6.2.7 LINGER

```
LINGER feature[:keyword=value] seconds
```

Rarely used. This causes the daemon to “hold on” to the license for *feature* for *seconds* after the application checks the license in or exits. This could be useful for short-duration programs which will be used many times in a row by the same user, to ensure that the user will be able to re-acquire the license repeatedly. On the other hand, other users have to wait until the first user is completely finished, plus a linger interval. This is useful only if the application uses duplicate grouping. Otherwise, LINGER will cause you to use extra licenses. Contact your software vendor for information about how they implemented duplicate grouping in their product.

If license lingering is set and `lmremove` is used to reclaim the license, `lmremove` will start, but not override, the license’s linger time.

6.2.8 MAX

(v5.11+ vendor daemon only.)

```
MAX num_lic feature[:keyword=value] type {list | group_name}
```

Limits usage for a group or user.

<i>num_lic</i>	Usage limit for this user or group.
<i>feature</i>	Feature this limit applies to.
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP.
<i>list</i>	List of <i>type</i> members to limit.
<i>group_name</i>	Name of the group to limit.

6.2.9 MAX_OVERDRAFT

```
MAX_OVERDRAFT feature[:keyword=value] num_lic
```

Limits OVERDRAFT license usage below the OVERDRAFT allowed by the license file.

6.2.10 NOLOG

```
NOLOG { IN | OUT | DENIED | QUEUED }
```

Suppresses logging the selected type of event in the debug log file.

To turn off logging of checkins:

```
NOLOG IN
```

To turn off logging of checkouts and queued requests two separate NOLOG lines are required:

```
NOLOG DENIED  
NOLOG QUEUED
```

Note: License administrators might use this option to reduce the size of the debug log file.

6.2.11 REPORTLOG

```
REPORTLOG [+]report_log_path
```

REPORTLOG specifies the report log file for this vendor daemon. We recommend preceding the *report_log_path* with a + character to append logging entries, otherwise the file will be overwritten each time the daemon is started.

Note: SAM*report*, a separate product available from GLOBEtrouter, is used to process FLEX*lm* report log files. SAM*report* can process only report log files, not debug log files.

REPORTING ON PROJECTS WITH LM_PROJECT

The SAM*report* report writer can report on “projects.” A project is set up by having all users working on a project set their LM_PROJECT environment variable (or registry on Windows) to a string that describes the project. SAM*report* can then group usage by project, as defined by what LM_PROJECT was set to when the application was run.

See also Appendix C, “FLEX*lm* Environment Variables.”

6.2.12 RESERVE

```
RESERVE num_lic feature[:keyword=value] type  
      {list | group_name}
```

Reserves licenses for a specific user.

<i>num_lic</i>	Number of license to reserve for this user or group.
<i>feature</i>	Feature this reservation applies to.
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP.
<i>list</i>	List of <i>type</i> members to reserve licenses for.
<i>group_name</i>	Name of group to reserve licenses for.

To reserve one license of feature “f1” for user “mel”:

```
RESERVE 1 f1 USER mel
```

Note: Any licenses reserved for a user are dedicated to that user. Even when that user is not actively using the license it will be unavailable to other users. However, a RESERVED license will not cause an overdraft to be reported by *SAMreport* if the license is not actually in use.

6.2.13 TIMEOUT

`TIMEOUT feature[:keyword=value] seconds`

Sets the time after which an inactive license is reclaimed by the vendor daemon.

<i>feature</i>	Name of the feature.
<i>seconds</i>	Number of seconds after which inactive license is reclaimed.

To set the timeout for feature “f1” to one hour (3600 seconds):

```
TIMEOUT f1 3600
```

TIMEOUT checks in the licenses if the process has been “idle” for a period longer than the specified time period. The daemon declares a process idle when it has not heard from the process (the client sends heartbeats). The application must explicitly declare itself idle for this to work, or (on UNIX) the application must be stopped (^Z). That is, unless the application explicitly supports this feature, it will not work. Contact your software vendor for information about how they implemented this feature in their product.

The application vendor can also disable the timeout feature, in which case the TIMEOUT option has no effect. The vendor can set a minimum value for the timeout. If you specify a timeout value smaller than the minimum, the minimum is used. The default minimum value is 900 seconds (15 minutes).

If you do not specify a timeout value in your options file, then there will be no timeout for that feature. With a pre-v5 vendor daemon, licenses are only freed by TIMEOUT when a new request for a license would require a license that can be freed with TIMEOUT. With v5+, licenses are freed when they time out.

6.2.14 TIMEOUTALL

(v5.11+ vendor daemon only.)

`TIMEOUTALL` *seconds*

Same as `TIMEOUT`, but applies to all features.

6.3 How the Vendor Daemon Uses the Options File

When the vendor daemon is started by `lmgrd`, the vendor daemon reads its options file. There can only be one options file per vendor daemon and each vendor daemon needs its own options file. `lmreread` does not cause the vendor daemon to reread its options file; for any changes in the options file to take effect, the vendor daemon must be restarted.

6.4 Rules of Precedence in Options Files

Before you can use options to utilize licenses effectively you must understand the options file precedence. `INCLUDE` and `EXCLUDE` statements can be combined in the same options file and control access to the same features. When doing so, keep in mind the following:

- If there is only an `EXCLUDE` list, everyone who is not on the list will be allowed to use the feature.
- If there is only an `INCLUDE` list, only those users on the list will be allowed to use the feature.
- If neither list exists, everyone is allowed to use the feature.
- The `EXCLUDE` list is checked before the `INCLUDE` list; someone who is on both lists will not be allowed to use the feature.

Once you create an `INCLUDE` or `EXCLUDE` list, everyone else is *implicitly* “outside” the group. This feature allows you, as an administrator, the ability to control licenses without having to *explicitly* list each user that you wish to allow or deny access to. In other words, there are two approaches; you can either:

- Give most users access and list only the exceptions, or
- Severely limit access and list only the those users that have access privileges

6.5 Options File Examples

The following information gives some examples of options files intended to illustrate ways to effectively control access to your licenses.

6.5.1 Simple Options File Example

```
RESERVE 1 compile USER robert
RESERVE 3 compile HOST mainline
EXCLUDE compile USER lori
NOLOG QUEUED
```

This options file would:

- Reserve one license for the feature “compile” for the user “robert.”
- Reserve three licenses for the feature “compile” for anyone on a computer with the host name “mainline.”
- Prevent the user “lori” from using the “compile” feature on any node on the network.
- Cause QUEUED messages to be omitted from the debug log file.

The sum total of the licenses reserved must be less than or equal to the number of licenses specified in the FEATURE line. In the example above, there must be a minimum of four licenses on the “compile” FEATURE line. If fewer licenses are available, only the first set of reservations (up to the license limit) is used.

If this data were in file `/a/b/xyzd/licenses/xyzd.opt`, then you would modify the license file DAEMON line as follows:

```
DAEMON xyzd /etc/xyzd /a/b/xyzd/licenses/xyzd.opt
```

6.5.2 Limiting Access for Multiple Users

Each INCLUDE, INCLUDEALL, EXCLUDE, EXCLUDEALL, and RESERVE line must have a single user name (or group) listed. To affect more than one user name create a GROUP. For example to exclude “bob,” “howard,” and “james” from using the feature called “toothbrush” we could create the following options file:

```
EXCLUDE toothbrush USER bob
EXCLUDE toothbrush USER howard
EXCLUDE toothbrush USER james
```

However, there is an easier way. Create a **GROUP** and exclude the list of users from using the feature. Like the previous example, the following options file would exclude “bob,” “howard,” and “james” from using the feature called “toothbrush”:

```
# First define the group "Hackers"
GROUP Hackers bob howard james
# Then exclude the group
EXCLUDE toothbrush GROUP Hackers
```

Now when you want to allow or deny access to any feature to that group, you have an alias list to make it simple.

With a *FLEXlm* v4+ vendor daemon, you can use **HOST_GROUP** to allow, deny, or reserve licenses for multiple hosts. For example, to exclude all users logged in on the hosts “fred” and “barney” from using a feature called “f1,” add these lines to your options file:

```
HOST_GROUP writers fred barney
EXCLUDE f1 HOST_GROUP writers
```

Note: See Section 6.2.3, “**GROUP**,” and Section 6.2.4, “**HOST_GROUP**,” for more information about defining groups.

6.5.3 EXCLUDE Example

```
#First Define the group "painters"
GROUP painters picasso mondrian klee
EXCLUDE spell GROUP painters
EXCLUDE spell USER bob
EXCLUDE spell INTERNET 123.123.123.*
```

This options file would:

- Prevent the users “picasso,” “mondrian,” and “klee” from using the feature “spell” on any machine on the network.
- Prevent the user “bob” from using the feature “spell” on any machine on the network.
- Prevent any user logged into a host with an IP address in the range 123.123.123.0 through 123.123.123.255 from using the feature “spell.”
- Allow any other user, as long as they are not on the excluded IP addresses, *and* they are not a member of the “painters” **GROUP**, *and* they are not “bob,” to use feature “spell” (by implication).

Note that “bob” could have been added to the group “painters.” However, “painters” might be used for some other purpose in the future so the license administrator chose to handle “bob” as a special case here. In this case, the two EXCLUDE statements concatenate to create a list of four users.

6.5.4 INCLUDE Example

```
INCLUDE paint USER picasso
INCLUDE paint USER mondrian
INCLUDE paint HOST bigbrush
```

This options file would:

- Allow the user “picasso” to use the feature “paint” on any machine on the network.
- Allow the user “mondrian” to use the feature “paint” on any machine on the network.
- Allow any user, as long as they are on the host “bigbrush,” to use feature “paint.”
- Deny access to the feature “paint” to anyone except “picasso,” “mondrian,” or anyone from the host “bigbrush” (by implication).

License Administration Tools

FLEX lm provides utilities for the license administrator to help manage the licensing activities on the network. These utilities are:

- `lmcksum` (v2.4+) — Prints license checksums.
- `lmdiag` (v4.0+) — Diagnoses license checkout problems.
- `lmdown` — Gracefully shuts down all license daemons (both `lmgrd` and all vendor daemons) on the license server node (or on all three nodes in the case of three-server redundant servers).
- `lmhostid` — Reports the hostid of a system.
- `lminstall` — Converts license files between different formats.
- `lmnewlog` — Moves existing report log information to a new file name and starts a new report log file with existing file name.
- `lmremove` — Releases a hung license to the pool of free licenses.
- `lmreread` — Causes the license daemon to reread the license file and start any new vendor daemons.
- `lmstat` — Displays the status of a license server.
- `lmswitchr` — Switches the report log to a new file name.
- `lmver` — Reports the FLEX lm version of a library or binary file.

This chapter also contains command-line syntax for `lmgrd`.

7.1 Running Administration Tools

Beginning in FLEX lm v2.4, all FLEX lm utility programs (except `lmgrd`) are packaged as a single executable called `lmutil`. `lmutil` can either be installed as the individual commands (either by creating links to the individual command names, or making copies of `lmutil` as the individual command names), or the commands can be run as `lmutil command`, for example, `lmutil lmstat`, or `lmutil lmdown`. On Windows systems, the `lmutil`

command forms of the commands are available. There is also a graphical user interface for these commands on Windows—see Section 7.15, “License Administration Tools—LMTOOLS for Windows.”

7.2 Universal Imutil Arguments

The following are valid arguments for all `lmutil` utilities:

<code>-c license_file_path</code>	Most <code>lmutil</code> utilities need to know the path to the license file. This can be specified with a <code>-c license_file_path</code> argument, or by setting the <code>LM_LICENSE_FILE</code> environment variable. Otherwise, the default location is used. Version 7+ utilities also honor all <code>VENDOR_LICENSE_FILE</code> environment variables. Some utilities can take more than one license file path in a license file list separated by colons on UNIX and semi-colons on Windows.
<code>-v</code>	Prints the FLEX lm version of the utility.
<code>-verbose</code>	Prints longer description for all errors found. The output from the utilities may be harder to read with this option, but is useful for diagnostics. (v6+ only)
<code>-e filename</code>	Redirects error message to a file. (v7+)

Note: The `lmdown`, `lmremove`, and `lmreread` commands are “privileged.” If you have started `lmgrd` with the `-2 -p` switch, you must be a license administrator to run any of these three utilities. A license administrator is a member of the UNIX “`lmadmin`” group, or, if the “`lmadmin`” group does not exist, a member of group 0. In addition, `lmgrd -x` can disable `lmdown` and/or `lmremove`.

7.3 lmcksum

The `lmcksum` program (FLEX`lm` v2.4 or later) will perform a checksum of a license file. This is useful to verify data entry errors at your location. `lmcksum` will print a line-by-line checksum for the file as well as an overall file checksum. `lmcksum` takes the `-k` switch to force the encryption key checksum to be case-sensitive.

`lmcksum` will ignore all fields that do not enter into the encryption key computation; thus the server node name and port number, the vendor daemon and options file paths, and lowercase `keyword=value` pairs on FEATURE/INCREMENT lines are not checksummed. In addition, `lmcksum` will treat non-case-sensitive fields correctly (in general, `lmcksum` is not case sensitive).

For FEATURE lines that contain `ck=nnn`, `lmcksum` prints simply OK or BAD.

Usage is:

```
lmcksum [-k] [-c license_file_path]
```

where `-c license_file_path` designates the license file to checksum. By default, `lmcksum` uses `license.dat` in the current directory (unlike other `lmutil` commands). Specify `-c license_file_path` if you want to checksum another license file.

Example output is:

```
lmcksum-Copyright (C) 1989, 1997 GLOBEtrotter Software, Inc.
lmcksum: using license file "/a/b/xyzd/licenses/license.dat189:
SERVER speedy 08002b32b161 2837

189: SERVER speedy 08002b32b161 2837
166: DAEMON xyzd C:\flexlm\xyzd.exe
8: FEATURE f1 xyzd 1.000 01-jan-2005 0 3B2BC333A0BF
OK: 231: FEATURE f2 xyzd 1.0 01-jan-0 1 8B1C3001535E \
      DUP_GROUP=HD ck=231
109: (overall file checksum)
```

7.4 lmdiag

`lmdiag` (FLEX`lm` v4.0 or later) allows you to diagnose problems when you cannot check out a license.

Usage is:

```
lmdiag [-c license_file_list] [-n] [feature[:keyword=value]]
```


where:

<code>-c license_file_list</code>	Diagnose the specified file(s).
<code>-n</code>	Run in non-interactive mode; <code>lmdiag</code> will not prompt for any input in this mode. In this mode, extended connection diagnostics are not available.
<code>feature</code>	Diagnose this feature only.
<code>keyword=value</code>	If a license file contains multiple lines for a particular feature, you can select a particular line for <code>lmdiag</code> to report on. For example: <code>lmdiag f1:HOSTID=12345678</code> will attempt a checkout on the line with the hostid "12345678." <code>keyword</code> can be one of the following: VERSION, HOSTID, EXPDATE, KEY, VENDOR_STRING, ISSUER

If no `feature` is specified, `lmdiag` will operate on all features in the license file(s) in your list. `lmdiag` will first print information about the license, then attempt to check out each license. If the checkout succeeds, `lmdiag` will indicate this. If the checkout fails, `lmdiag` will give you the reason for the failure. If the checkout fails because `lmdiag` cannot connect to the license server, then you have the option of running "extended connection diagnostics."

These extended diagnostics attempt to connect to each port on the license server node, and can detect if the port number in the license file is incorrect. `lmdiag` will indicate each port number that is listening, and if it is an `lmgrd` process, `lmdiag` will indicate this as well. If `lmdiag` finds the vendor daemon for the feature being tested, then it will indicate the correct port number for the license file to correct the problem.

See also Section B.2, "FLEXLM_DIAGNOSTICS."

7.5 lmdown

The `lmdown` utility allows for the graceful shutdown of all license daemons (both `lmgrd` and all vendor daemons) on all nodes.

Usage is:

```
lmdown [-c license_file_list] [-vendor vendor] [-q] [-all]
```

where:

<code>-c <i>license_file_list</i></code>	Use the specified license file(s).
<code>-vendor <i>vendor</i></code>	Shut down only this vendor daemon. <code>lmgrd</code> will always continue running if this option is specified. Requires v6.0 <code>lmdown</code> and <code>lmgrd</code> (the vendor daemon can be any version).
<code>-q</code>	Don't prompt or print a header. Otherwise <code>lmdown</code> asks "Are you sure? [y/n]: ."
<code>-all</code>	If multiple servers are specified, automatically shuts down all of them. Otherwise, only one is shutdown. <code>-q</code> is implied with <code>-all</code> . (v7+)

You may want to protect the execution of `lmdown`, since shutting down the servers causes users to lose their licenses. See the `-2 -p` or the `-x` options in Section 7.6, "lmgrd," for details about securing access to `lmdown`.

If `lmdown` encounters more than one server (for example if `-c` specifies a directory with many `*.lic` files), a choice of license servers to shut down is presented.

Note: Do not use `kill -9` to shut down the license servers.

To stop and restart a single vendor daemon, use `lmdown -vendor vendor`, then use `lmreread -vendor vendor` to restart the vendor daemon.

When shutting down redundant servers, there is a one-minute delay before the servers shut down. `lmdown` will shut down all three license servers of a set of redundant license servers. If you need to shut down one of a set of redundant

license servers (not recommended because you are left with two points of failure), you must kill both the `lmgrd` and vendor daemon processes on that license server machine.

See also Section 7.11, “lmreread.”

7.6 lmgrd

`lmgrd` is the main daemon program for *FLEXlm*. When you invoke `lmgrd`, it looks for a license file which contains information about vendors and features. On UNIX systems, it is strongly recommended that `lmgrd` be run as a non-privileged user (not root).

Usage is:

```
lmgrd [-c license_file_list] [-l debug_log_path]
      [-2 -p] [-nfs_log] [-x lmdown] [-x lmremove] [-z ] [-v]
```

where:

- | | |
|--|---|
| <code>-c <i>license_file_list</i></code> | Use the specified license file(s). |
| <code>-l <i>debug_log_path</i></code> | Write debugging information to file <i>debug_log</i> . This option uses the letter <code>l</code> , not the numeral <code>1</code> . |
| <code>-2 -p</code> | Restricts usage of <code>lmdown</code> , <code>lmreread</code> , and <code>lmremove</code> to a <i>FLEXlm</i> administrator who is by default root. If there a UNIX group called “ <code>lmadmin</code> ,” then use is restricted to only members of that group. If root is not a member of this group, then root does not have permission to use any of the above utilities. If <code>-2 -p</code> is used when starting <code>lmgrd</code> , no user on Windows can shut down the license server with <code>lmdown</code> . |

<code>-nfs_log</code>	We do not recommend writing a debug log to an NFS-mounted or PC network-mounted disk. If you choose to write to a mounted disk and the speed of the license server is too slow, you can use this flag to cache debug info before it is written out (when approximately 1kb of data is reached).
<code>-x lmdown</code>	Disable the <code>lmdown</code> command (no user can run <code>lmdown</code>). If <code>lmdown</code> is disabled, you will need to stop <code>lmgrd</code> via <code>kill pid</code> (UNIX) or stop the <code>lmgrd</code> and vendor daemon processes through the Task Manager or NT Service (Windows). On UNIX, be sure the <code>kill</code> command does not have a <code>-9</code> argument. (v4+ <code>lmgrd</code>)
<code>-x lmremove</code>	Disable the <code>lmremove</code> command (no user can run <code>lmremove</code>). (v4+ <code>lmgrd</code>)
<code>-z</code>	Run in foreground. The default behavior is to run in the background. Windows: pre-v7, <code>lmgrd</code> always runs in the foreground. In v7+, <code>lmgrd</code> runs in the background by default. If <code>-l debug_log_path</code> is present, then no windows are used, but if no <code>-l</code> argument specified, separate windows are used for <code>lmgrd</code> and each vendor daemon.
<code>-v</code>	Prints <code>lmgrd</code> version number and copyright and exits.

Note: Pre-v6 `lmgrd` on Windows required `-app` argument when not run as a service.

7.7 lmhostid

The `lmhostid` utility reports the hostid of a any machine whose platform is supported by *FLEXlm*. The default hostid type is displayed for a platform, unless an optional hostid type is specified and supported by that platform.

Usage is:

```
lmhostid [-n] [type]
  where type is one of:
  [-internet] (optional on all platforms)
  [-vsn] [-flexid] [-cpu[32|64|96]] (optional on Windows)
  [-ether] (optional on HP)
```

<code>-n</code>	No header is printed, only the hostid is printed.
<code>-internet</code>	IP address in ###.###.###.### format.
<code>-vsn</code>	Volume Serial Number of the Windows C:\ drive.
<code>-flexid</code>	GLOBEtrötter dongle-based hostid. (Windows)
<code>-cpu[32 64 96]</code>	Pentium III hostid for Windows. Requires <i>FLEXlm</i> v7.0d+. The <code>cpuid</code> is turned off by default, so it must be enabled, which is normally performed in the BIOS Setup (usually pressing the DEL key during system boot). The full ID is 96-bit, and this is what must be used for a truly unique ID, but duplicate 32-bit hostids are expected to be rare, if they occur at all. Where available, this the recommended hostid type.
<code>-ether</code>	Ethernet address. On HP, the default hostid is the true system hostid (from <code>uname -i</code>), and is recommended, but partly for historic reasons, the ethernet address is also available as a hostid.

The output of this command looks as follows:

```
lmhostid - Copyright (c) 1989, 1997 Globetrotter Software, Inc.
The FLEXlm hostid of this machine is "69021c89"
```

See also Appendix A, “Hostids for FLEXlm-Supported Machines.”

7.8 lminstall

Introduced in v6.0, `lminstall` is designed primarily for typing in decimal format licenses to generate a readable format license file.

Usage is:

```
lminstall [-i in_lic_file ] [-maxlen n] \  
[-o out_lic_file] \  
[-overfmt {2 | 3 | 4 | 5 | 5.1 | 6 | 7 | 7.1}] [-odecimal]
```

Normally, to convert from decimal to readable format, `lminstall` is used with no arguments; you are prompted for the name of the output license file. The default file name is today’s date in `yyyymmdd.lic` format. The file should be moved to the application’s default license file directory, if specified by the software vendor. Otherwise, use the `LM_LICENSE_FILE` or `VENDOR_LICENSE_FILE` environment variables to specify the directory where the `*.lic` files are located.

Decimal format input is verified by a checksum of each line.

To finish entering, type `q` on a line by itself or enter two blank lines.

When an input file is specified with no output file specified, output goes to `stdout`; if neither input nor output file is specified, `lminstall` assumes that input will come from `stdin` and prompts the user for an output file name.

`lminstall` can also be used to convert licenses from readable to decimal format, and between different versions of FLEXlm license formats.

To convert from readable to decimal:

```
lminstall -i in_lic_file -o out_lic_file -odecimal
```

To convert to FLEXlm v5.1 format:

```
lminstall -i in_lic_file -o out_lic_file -overfmt 5.1
```

To enforce a maximum line length of, for example, 50 characters:

```
lminstall -maxlen 50
```

Conversion errors are reported as necessary. `lminstall` has a limit of 1000 lines of input.

7.9 lmnewlog

The `lmnewlog` utility switches the report log file by moving the existing report log information to a new file, then starting a new report log with the original report log file name. If you rotate report logs with `lmnewlog` instead of `lmswitchr`, you will not have to change the file name in the `REPORTLOG` line of the vendor's options file.

Usage is:

```
lmnewlog [-c license_file_list] feature renamed_report_log
```

or:

```
lmnewlog [-c license_file_list] vendor renamed_report_log
```

where:

<code>-c license_file_list</code>	Use the specified license file(s).
<code>feature</code>	Any feature in this license file.
<code>vendor</code>	Vendor daemon in this license file.
<code>renamed_report_log</code>	New file path where existing report log information is to be moved.

Note: `lmnewlog` works only with `FLEXlm v7+` vendor daemons. Ask your vendor for an updated version of their vendor daemon.

7.10 lmremove

The `lmremove` utility allows you to remove a single user's license for a specified feature. This is only needed when a client node crashes, since that's the only condition where a license is not automatically freed. If the application is active, it will re-checkout the license after it is freed by `lmremove`.

Usage is:

```
lmremove [-c license_file_list] feature user user_host display
```

or

```
lmremove [-c license_file_list] -h feature server_host port handle
```

where:

<i>-c license_file_list</i>	Specify license file(s).
<i>feature</i>	Name of the feature checked out by the user.
<i>user</i>	Name of the user whose license you are removing, as reported by <code>lmstat -a</code> .
<i>user_host</i>	Name of the host the user is logged into, as reported by <code>lmstat -a</code> .
<i>display</i>	Name of the display where the user is working, as reported by <code>lmstat -a</code> .
<i>server_host</i>	Name of the host on which the license server is running.
<i>port</i>	Port number where the license server is running, as reported by <code>lmstat -a</code> .
<i>handle</i>	License handle, as reported by <code>lmstat -a</code> .

The *user*, *user_host*, *display*, *server_host*, *port*, and *handle* information must be obtained from the output of `lmstat -a`.

`lmremove` removes all instances of *user* on *user_host* and *display* from usage of *feature*. If the optional *-c license_file_list* is specified, the indicated file(s) is used as the license file. You should protect the execution of `lmremove`, because removing a user's license can be disruptive. See the *-x* or *-2 -p* options in Section 7.6, "lmgrd," for details about securing access to `lmremove`.

The *-h* variation uses the *server_host*, *port*, and license *handle*, as reported by `lmstat -a`. Consider this example `lmstat -a` output:

```
joe nirvana /dev/tty5 (v1.000) (cloud9/7654 102), start Fri 10/29 18:40
```

In this example, the user is "joe," the user host is "nirvana," the display is "/dev/tty5," the server host is "cloud9," the port is "7654," and the license handle is "102."

lmreread

To remove this license, issue one of the following commands:

```
lmremove f1 joe nirvana /dev/tty5
```

or

```
lmremove -h f1 cloud9 7654 102
```

When removing by handle, if licenses are grouped as duplicates, all duplicate licenses will also be removed. If license lingering is set and `lmremove` is used to reclaim the license, `lmremove` will start, but not override, the license's linger time.

7.11 lmreread

The `lmreread` utility causes the license daemon to reread the license file and start any new vendor daemons that have been added. In addition, all running daemons will be signaled to reread the license file for changes in feature licensing information. If the optional vendor daemon name is specified, only the named daemon will reread the license file (in this case, `lmgrd` will not reread the license file).

Usage is:

```
lmreread [-c license_file_list] [-vendor vendor] [-all]
```

where:

<code>-c <i>license_file_list</i></code>	Use the specified license file(s).
<code>-vendor <i>vendor</i></code>	Only this one vendor daemon should reread the license file. <code>lmgrd</code> will restart the vendor daemon if necessary. Requires v6+ <code>lmreread</code> and <code>lmgrd</code> (the vendor daemon can be any version).
<code>-all</code>	If more than one <code>lmgrd</code> is specified, instructs all <code>lmgrds</code> to reread. (v7+)

You may want to protect the execution of `lmreread`. See the `-2 -p` and `-x` options in Section 7.6, “`lmgrd`,” for details about securing access to `lmreread`.

To stop and restart a single vendor daemon, use `lmdown -vendor vendor`, then use `lmreread -vendor vendor`, which restarts the vendor daemon.

Note: If you use the `-c license_file_list` option, the license file(s) specified will be read by `lmreread`, not by `lmgrd`; `lmgrd` rereads the file it read originally. Also, `lmreread` cannot be used to change server node names or port numbers.

Note: Vendor daemons will not reread their option files as a result of `lmreread`.

7.12 lmstat

The `lmstat` utility helps you monitor the status of all network licensing activities, including:

- Daemons that are running
- Users of individual features
- Users of features served by a specific vendor daemon

`lmstat` prints information that it receives from the license server, therefore it will not return any information about users of node-locked uncounted or DEMO licenses, unless the server's license file includes the node-locked licenses and the client is not reading the license file (via `@host, port@host` or `USE_SERVER`). Queued users and licenses shared due to duplicate grouping are also not returned by `lmstat`.

Usage is:

```
lmstat [-a] [-A] [-c license_file_list] [-f [feature]]
      [-S [vendor]]
```

where:

<code>-a</code>	Display all information about.
<code>-A</code>	List all active licenses.
<code>-c license_file_list</code>	Use the specified license file(s).
<code>-f [feature]</code>	List users of <i>feature</i> .
<code>-S [vendor]</code>	List all users of <i>vendor</i> 's features.

lmstat

lmremove requires the output of `lmstat -a`. The output of `lmstat -a` looks similar to:

```
License server status: 27000@myhost1
License file(s) on myhost: /flexlm/v7.2/sun4_u5/license.dat:
myhost: license server UP (MASTER) v7.2
Vendor daemon status (on myhost1):

demo: UP v7.2
Feature usage info:
Users of f1: (Total of 4 licenses available)
  "f1" v1.0, vendor: demo
floating license
  daniel myhost2 19.16.18.26 (v1.0) (myhost1/27000 102), start Fri
    5/3 7:29
```

where:

daniel	<i>user</i>	User name.
myhost2	<i>user_host</i>	Host where user is running.
19.16.18.26	<i>display</i>	Display where user is running.
v1.0	<i>version</i>	Version of feature.
myhost1	<i>server_host</i>	Host where license server is running.
27000	<i>port</i>	Port on <i>server_host</i> where license server is running.
102	<i>handle</i>	License handle.
start Fri 5/3 7:29	<i>checkout_time</i>	Time that this license was checked out.

Note: `lmstat -a` is a potentially expensive command. With many active users, this can generate a lot of network activity, and therefore should not be used too often.

7.13 lmswitchr

The `lmswitchr` utility switches the report log file by closing the existing report log and starting a new report log with a new file name. It will also start a new report log file if one does not already exist.

Usage is:

```
lmswitchr [-c license_file_list] feature new_report_log
```

or with v5+ vendor daemon:

```
lmswitchr [-c license_file_list] vendor new_report_log
```

where:

<code>-c <i>license_file_list</i></code>	Use the specified license file(s).
<code><i>feature</i></code>	Any feature in this license file.
<code><i>vendor</i></code>	Vendor daemon in this license file.
<code><i>new_report_log</i></code>	Path to new report log file.

Note: `lmswitchr` does not work with FLEXlm v3.0 vendor daemons. Ask your vendor for a later version of their vendor daemon.

7.14 lmver

The `lmver` utility reports the FLEXlm version of a library or binary file.

Usage is:

```
lmver filename
```

where *filename* is the name of an executable file built with FLEXlm.

For example if you have an application called “spell,” type:

```
lmver spell
```

Alternatively, on UNIX systems, you can use the following commands to get the FLEXlm version of a binary:

```
strings filename | grep Copy
```

7.15 License Administration Tools—LMTOOLS for Windows

For the 32-bit Windows platforms, an LMTOOLS program is provided.

With LMTOOLS, you can start, stop and configure FLEXlm license servers, get system information, including hostids, get server status, and more.

LMTOOLS v7+ has two modes in which to configure a license server:

- Configuration using a license file
- Configuration using services

7.15.1 Configuration Using License File

Operations are performed on a particular license file. In this mode, you cannot start the `lmgrd` process, but you can do everything else. In the first tab, you need to select a license file.

7.15.2 Configuration Using Services

Operations are performed on a Windows Service, which allows starting `lmgrd` processes. On NT, you configure a real NT Service. On Windows 95/98, it behaves similarly to an NT service. In the first tab, you need to select a service.

Use the Configure Services tab to define a license service. When configuring a service, a license file is selected (similar to Configuration using License File), but in addition, locations for `lmgrd` and the debug log file are specified, the service is given a unique name, and you can also indicate that the service should be started with system boot.

Hostids for FLEX/m-Supported Machines

FLEX/m uses different machine identifications for different machine architectures. For example, all Sun Microsystems machines have a unique hostid, whereas all DEC machines do not. For this reason, the ethernet address is used on some machine architectures as the hostid. An ethernet address is a 6-byte quantity, with each byte specified as two hexadecimal digits. Specify all twelve hex digits when using an ethernet address as a hostid. For example, if the ethernet address is “8:0:20:0:5:ac,” you would specify “0800200005ac” as the hostid.

A.1 Hostid Formats

Numeric, 32-bit hostids are normally used in hexadecimal format. On some systems, including HP and SGI, the system command returns the number in decimal format. Since v3.0 of FLEX/m, a “#” before the hostid indicates to FLEX/m that this is a decimal number. For example, if the HP `uname -i` command returns “2005771344,” FLEX/m will accept “#2005771344.” Or it can be converted to hexadecimal. On UNIX systems, you can convert to hex with the following script:

```
echo 2005771344 16o p | dc
778DA450
```

A.2 Expected FLEX/m Hostids

The program `lmhostid` will print the exact hostid that FLEX/m expects to use on any given machine. The following table lists alternate methods to obtain the required hostid for each machine architecture. FLEX/m also supports a group of special hostids and vendor-defined hostids.

Hardware Platform	Hostid	Type this command on the license server:	Example
AIX (RS/6000, PPC)	32-bit hostid	<code>uname -m</code> (returns 000276513100), then remove last two digits, and use remaining last eight digits	02765131
DEC Alpha	ethernet address	<code>netstat -i</code>	080020005532
HP	32-bit hostid	<code>uname -i</code> and convert to hex, or prepend with #	778DA450 or #2005771344
	ethernet address	<code>lanscan</code> (station address without leading "0x")	0000F0050185
Linux	ethernet address	<code>/sbin/ifconfig eth0</code> and remove colons from HWaddr 00:40:05:16:E5:25	00400516E525
SCO	Hostid String	<code>uname -x</code> (Serial is SCO00354), then prefix with "ID_STRING="	ID_STRING=SCO00354
SGI	32-bit hostid	<code>/etc/sysinfo -s</code> , convert to hex, or prefix #	69064C3C or #1762020412
SUN	32-bit hostid	<code>hostid</code>	170a3472

Hardware Platform	Hostid	Type this command on the license server:	Example
Windows	ethernet address	<code>lmutil lmhostid</code>	00B0A9DF9A32
	Disk serial number	DIR C: (look for “Volume Serial Number is”, and remove “-”)	DISK_SERIAL_NUM=3e2e17fd
	Dongle—parallel port hardware key	<code>lmhostid -flexid</code>	FLEXID=7-b28520b9
	Pentium III+ CPU, V7.0d+ only. Use BIOS Setup to enable.	<code>lmhostid -cpu</code> <code>lmhostid -cpu96</code> (The 32-bit version is the last nine characters from the full id.)	9077-5D77-0002-57C8-95D2-1D3D (96-bit) 95D2-1D3D (32-bit)

A.3 Special FLEXlm Hostids

FLEXlm contains a number of “special” hostid types which apply to all platforms. These hostid types can be used on either a SERVER line or a FEATURE line, wherever a hostid is required. These are:

ANY	Locks the software to any node (i.e., does not lock anything).
DEMO	Similar to ANY, but only for use with uncounted FEATURE lines.
DISK_SERIAL_NUM= <i>SN</i>	Locks the software to a PC with C drive serial number <i>SN</i> . (Windows only).
DISPLAY= <i>display</i>	Locks the software to display <i>display</i> .
FLEXID= <i>SN</i>	Locks the software to a PC with a hardware key (dongle) of serial number <i>SN</i> . (Windows only).

<code>HOSTNAME=<i>host</i></code>	Locks the software to computer host name <i>host</i> .
<code>ID=<i>n</i></code>	Functionally equivalent to the “ANY” hostid—it will run on any node. The difference is that the license is unique and can be used to identify the customer. This hostid can be used to lock the license server (on the SERVER line) or the client (on the FEATURE/INCREMENT line). The number can have dashes included for readability—the dashes are ignored. Examples: ID=12345678 is the same as ID=1234-5678 is the same as ID=1-2-3-4-5-6-7-8
<code>ID_STRING=<i>string</i></code>	Used on SCO systems for hostid.
<code>INTERNET= ###.###.###.###</code>	Locks the software to an Internet IP address, or group of IP addresses. Wildcards are allowed. For example, 198.156.*.* means any host with a matching internet IP address. The main use is to limit usage access by subnet, implying geographic area. For this purpose, it would be used on the FEATURE/INCREMENT line, as a hostid lock.
<code>USER=<i>user</i></code>	Locks the software to user name <i>user</i> .

EXAMPLES

```
FEATURE f1 demo 1.0 1-jan-2005 uncounted HOSTID=HOSTNAME=globes \  
SIGN=AB28E0011DA1
```

OR

```
FEATURE f1 demo 1.0 1-jan-2005 uncounted HOSTID=USER=joe \  
SIGN=EB78201163B0
```

Troubleshooting Guide

This appendix documents areas of FLEX lm that have given customers difficulty in the past. We hope it helps you debug any problems you might experience at your site.

B.1 General Debugging Hints

The following are tips for debugging:

- When you start the license server (`lmgrd`) be sure that you direct the output into a log file where you can examine it. The log file often contains useful information. You should examine it when you have a problem, and be prepared to answer questions about it when you talk to a support person.
- If the license server appears to have started correctly (which you should be able to determine from the log file), try running `lmstat -a` and `lmdiag` to see if that program has the same problem as your application.
- If your application is FLEX lm v4.1 or later (v5 or later on Windows), you can use the `FLEXLM_DIAGNOSTICS` environment variable. Set `FLEXLM_DIAGNOSTICS` to 1, 2, or 3. A setting of 3 gives more information than 2, 2 gives more information than 1 (in particular, the feature name that was denied).
- When you talk to a support person, you should be prepared to answer the following questions:
- What kind of machine is your license server running on? What version of the operating system? What machine and operating system is the application running on?
- What version of FLEX lm does the program use? Use the `lmver` script, or, on UNIX, execute the following command on your `lmgrd`, vendor daemon, and application:

```
strings binary_name | grep Copy
```

Alternatively, `lmgrd -v` gives the `lmgrd` version, and this works with the vendor daemon also.

- What error or warning messages appear in the log file? Did the server start correctly? Look for a message such as:

```
server xyz started for: feature1 feature2.
```
- What is the output from running `lmstat -a`?
- Are you running other products which are also licensed by FLEXlm? Are you using a combined license file or separate license files?
- Are you using redundant servers (multiple SERVER lines in your license file)?

B.2 FLEXLM_DIAGNOSTICS

Note: Available only with applications using FLEXlm v4.1 or higher for UNIX, and v5.0 or higher with Windows. Also, applications may choose not to provide this functionality.

FLEXLM_DIAGNOSTICS is an environment variable that will cause the application to produce diagnostic information when a checkout is denied. The format of the diagnostic information may change over time.

To set FLEXLM_DIAGNOSTICS, on UNIX:

```
(csh): setenv FLEXLM_DIAGNOSTICS 1
(sh): FLEXLM_DIAGNOSTICS=1; export FLEXLM_DIAGNOSTICS
```

On Windows 3.1 and 95, add the following line to `C:\autoexec.bat`:

```
SET FLEXLM_DIAGNOSTICS=1
```

On NT, use the System Control Panel applet to change the global environment, adding FLEXLM_DIAGNOSTICS to 1.

On UNIX, the diagnostic output goes to `stderr`.

On Windows, if the application is v5.11 or higher, the output is a file in the current directory called `flexpid.log`, where *pid* is the application's process ID. If the application is v5.0, the output file is called `flex_err.log`.

B.2.1 Level 1 Content

If FLEXLM_DIAGNOSTICS is set to 1, then the standard FLEXlm error message will be presented, plus a complete list of license files that the application tried to use. For example:

```
setenv FLEXLM_DIAGNOSTICS 1
FLEXlm checkout error: Cannot find license file (-1,73:2) No such file
or directory
license file(s): /usr/myproduct/licenses/testing.dat license.dat
```

B.2.2 Level 2 Content

If FLEXLM_DIAGNOSTICS is set to 2, then, in addition to level 1 output, the checkout arguments are presented. For example:

```
setenv FLEXLM_DIAGNOSTICS 2
FLEXlm checkout error: No such feature exists (-5,116:2) No such file or
directory
license file(s): /usr/myproduct/licenses/testing.dat license.dat
lm_checkout("f1", 1.0, 1, 0x0, ..., 0x4000)
```

Note that the error message actually contains two separate problems, which both occurred during the checkout:

- There's no such feature in the license it did find
- It was unable to find the other license file, which is what produces the message "No such file or directory"

Following is a description of the arguments to `lm_checkout()`

```
lm_checkout(feature, version, num_lic, queue_flag, ...,
            dupgroup_mask)
```

where:

<i>feature</i>	The requested feature.
<i>version</i>	The requested version. The license file must contain a version \geq the requested version.
<i>num_lic</i>	Number of licenses requested. Usually 1.
<i>queue_flag</i>	If 0, no queueing If 1, queue for license ("blocking" queue) If 2, queue for licenses, but return to application ("non-blocking" queue)
<i>dupgroup_mask</i>	Indicates duplicate grouping, also called license sharing. User, host, and display are as shown by <code>lmstat -a</code> .

B.2.3 Level 3 Content (FLEXlm v6+ only)

If `FLEXLM_DIAGNOSTICS` is set to 3, then, in addition to level 1 and 2 output, if a checkout is successful, information is printed explaining how the license was granted:

```
setenv FLEXLM_DIAGNOSTICS 3
app
Checkout succeeded: f0/14263EAEA8E0
License file: ./servtest.lic
No server used
app2
Checkout succeeded: f1/BC64A7B120AE
License file: @localhost
License Server: @localhost
app3
Checkout succeeded: f1/BC64A7B120AE
License file: servtest.lic
License Server: @speedy
```

Note that the feature name and license key are printed, along with the license file location (or host name if `@host` were used) and host name of the server, where applicable.

B.3 FLEXlm Troubleshooting List

B.3.1 Problem Description Format

Each problem is presented in three parts:

- Symptom:** *A description of the problem.*
- Cause:** A discussion of what causes the problem described in the “Symptom” section.
- Solution:** Instructions on how to solve the problem.

You can scan through the list of problems to find any which appear to relate to your concerns. In order to solve your problem, you may have to use all or some of the solutions listed here.

B.3.2 Hostid Problems

Symptom: *When I run the license manager on my machine, it tells me it is the wrong hostid.*

Cause: The vendor daemon checks the hostid listed on the SERVER line in the license file; if it does not match the hostid of the machine it is running on, this message will be printed. Possible causes include: 1) you are trying to run the license server on a different machine from the machine the file was made for; 2) the hostid of the machine you are running on changed (for example, the dongle hostid was moved (Windows) or the CPU board was replaced); 3) the hostid in the license file was modified.

Solution: Verify that the hostid of the machine on which the vendor daemon (or node locked client program) is being run matches the hostid specified in the license file (on the SERVER line for the vendor or on the FEATURE line for a node-locked client). You can run the `lmhostid` program to see what FLEXlm thinks the hostid is. You may not modify the hostid in the license file. If the hostid of your server machine changes, you will have to get a new license file from your software vendor.

B.3.3 Connection Problems

- Symptom:** *The application program (or `lmstat`) can't connect to the server to check out a license.*
- Cause:** The FLEXlm routines in the application are unable to make a TCP connection to the server and port specified in the license file. Possible reasons for this are: 1) the wrong license file is being referenced by the application program; 2) the server machine specified in the license file is down; 3) the vendor daemon specified in the license file is not running; 4) the host name in the license file is not recognized by the system; 5) the network between the client machine and the server machine is down; 6) You are mixing FLEXlm v1.5 (or earlier) and v2.1 (or later) vendor daemons in one license file and have run `lmgrd` without the `-b` command line option; 7) TCP is not running on your machine.
- Solution:** The `lmdiag` utility is designed primarily to debug this problem, so first, try `lmdiag`. Verify that the application is using the proper license file. Verify that specified server machine is up and reachable by executing another command that uses TCP, such as `telnet`, from the client to the server. Verify that the vendor daemon is running (you can use `ps` on the server to look for it). Examine the license log file to see if any problems are reported, particularly messages indicating that the vendor daemon has quit. Run `lmstat -a` from the server machine to verify that the vendor daemon is alive. Run `lmstat -a` from the client machine to verify the connection from client to vendor daemon across the network. Try using `telnet host port` where `host` and `port` are the same as on the SERVER line in your license file.

B.3.4 Other Client Problems

Symptom: *When I run my application program (or vendor daemon), I get the error bad code or inconsistent encryption code.*

Cause: Possible causes for this are: 1) the license file was modified (either the hostid on a SERVER line or anything on the FEATURE line was changed); 2) the vendor used the wrong version of his license creation program to generate your license file (or there is a bug in that process).

Solution: You may not modify the license file (except for specific fields, see Chapter 3, “The License File”). If you need to change something in your license file, you must get a new license file from your software vendor.

Symptom: *When the second user tries to check out a license, the vendor daemon prints an error concerning Parameter mismatch in the debug log file and refuses the license. The application may give the error: Duplicate selection mismatch for this feature.*

Cause: The most likely cause of this problem is that you are simultaneously trying to run two different versions of the application program, and the software vendor has not specifically set up the new version for this kind of compatibility. Check the debug log file for a comm version mismatch warning message; this indicates that someone is running an older client than the license server daemon, lmgrd.

Solution: Run only the new version of the application (or only the old version).

B.3.5 Other Server Problems

Symptom: *When I run the vendor daemon on my VMS system, I get the error message `socket bind: permission denied (13)`.*

Cause: The daemon needs to bind the socket address in order to be able to listen for connections from clients. This is done in the system name table, so it requires the SYSNAM privilege.

Solution: Run the daemon in a process with the SYSNAM privilege set.

- Symptom:** *When I start up lmgrd, it says execl failed on my vendor daemon.*
- Cause:** lmgrd uses execl to start each vendor daemon running. If there is a problem starting the vendor daemon, this message is output to the log file. This error is typically caused by one of the following: 1) there is no executable at the location referred to by the license file (and printed out in the log file); 2) the executable does not have the proper permissions to be run (the file does not have the “x” bit set or one of the directories in the path is not readable); 3) there was an error building the executable, and it can not be run; 4) the executable is for a different machine architecture.
- Solution:** Verify that the path to the vendor daemon is absolute (i.e., starts with a slash character and that it points to the executable program itself, not the containing directory (for FLEXlm v1.5). Ensure that the file exists by doing an `ls -l` of the vendor daemon file name(s) specified in the log file. Make sure you do this as the same user that started lmgrd. Verify that the file is executable. Note that if you are running as root and using an NFS-mounted file system, the relevant protection bits are the “other” bits (not the “user” bits), even if the file is owned by root. Do a `whatis` on the file (if your system has that program). `whatis` should tell you the file is an executable for the machine you are trying to run it on. Run the vendor daemon directly from the command line. If the vendor daemon is properly linked, it will tell you that it must be run from lmgrd; if it crashes or fails to execute, then it is not properly linked.

- Symptom:** *The license server keeps reporting “lost lock” errors in the log file and exiting.*
- Cause:** The lock file (normally placed in `/usr/tmp` on UNIX, `C:\flexlm` on Windows NT, `SYS:\SYSTEM\FLEXLM` on Netware) is being removed by someone else. There could be another daemon running, or the license administrator (or a script he set up) could have deleted the file.
- Solution:** Check to see if there is more than one copy of the daemon running. On UNIX use a command like `ps -aux | grep vendor` to search for it. Check for more than one `lmgrd` running as well, since it will restart your vendor daemon when it is killed. If more than one `lmgrd` is running, kill them all (using the `kill` command, not `kill -9`, on UNIX or LMTOOLS on Windows NT), then kill any remaining vendor daemons (on UNIX, try a simple `kill`, if that fails then try `kill -9` the `lmgrd` and all vendor daemons) and start one fresh copy of `lmgrd`. On UNIX, check to see if there is a shell script running that cleans out `/tmp` (or `/usr/tmp`). If so, try modifying it so that it does not delete zero-length files.

FLEXlm Environment Variables

Environment variables should never be required to use FLEXlm-licensed applications. Environment variables are normally used for debugging or for changing license default location.

C.1 How to Set Environment Variables

FLEXlm environment variables are set in two different ways:

- The normal `set` or `setenv` commands (or the System Control Panel on Windows NT)
- The registry (Windows v6+) or in `$HOME/.flexlmrc` (UNIX v7+), which functions like the registry for FLEXlm on UNIX.

C.1.1 Registry

On Windows, the FLEXlm registry location is:

```
HKEY_LOCAL_MACHINE→SOFTWARE→FLEXlm License Manager
```

On UNIX, the equivalent information is stored in `$HOME/.flexlmrc`. In this file, the syntax is `variable=value`.

C.1.2 Precedence

If the variable is `LM_LICENSE_FILE` or `VENDOR_LICENSE_FILE`, then both the environment and the registry are used, with the environment used first, and the registry appended to the path.

If it's a different variable, then if the environment set, only that is used, otherwise the registry is used. That is, the registry is only used if the environment is not set.

C.2 Environment Variables

Variable	Use (<i>FLEXlm</i> version introduced)
FLEXLM_BATCH	Windows only: prevents interactive pop-ups from appearing. Set to 1 if a batch application. (Version 7+ clients)
FLEXLM_DIAGNOSTICS	Used for debugging where applications don't print <i>FLEXlm</i> error message text. Set to 1, 2, or 3, depending on the amount of diagnostic information desired. See Section B.2, "FLEXLM_DIAGNOSTICS." (Version 5+ clients)
LM_LICENSE_FILE or VENDOR_LICENSE_FILE	Reset path to license file. Can be a license file list, separated by ":" on UNIX and ";" on Windows. If <i>VENDOR_LICENSE_FILE</i> used, <i>VENDOR</i> is the vendor daemon name used by this application. For example, GLOBEtrötter Software products use <i>GSI_LICENSE_FILE</i> . Can be a file name, or <i>port@host</i> . See also Section 3.1.2, "Setting the Path with an Environment Variable." (<i>VENDOR_LICENSE_FILE</i> requires v6+ clients.)
LM_PROJECT	LM_PROJECT's value is logged in the report log file and later reported on by <i>SAMreport</i> . Limited to 30 characters. (Version 5+ client required.) This can also be used to RESERVE, INCLUDE, etc. licenses with PROJECT. For example: <pre>RESERVE 1 fl PROJECT airplane</pre> v5+ clients and v7+ vendor daemon are required for this feature.

Frequently Asked Questions

D.1 License File Questions

D.1.1 I've received FLEX lm license files from two different companies. Do I have to combine them?

You don't have to combine license files. Each license file that has any counted lines (the license count field is > 0) requires a server. It's perfectly OK to have any number of separate license files, with different `lmgrd` server processes supporting each file. Moreover, since `lmgrd` is a lightweight process, for sites without system administrators, this is often the simplest (and therefore recommended) way to proceed. With v6+ `lmgrd/lmdown/lmreread`, you can restart/stop/reread a single vendor daemon (of any FLEX lm version). This makes combining licenses more attractive than previously. Also, if the application is v6+, using `dir/*.lic` for license file management behaves like combining licenses without physically combining them.

D.1.2 When is it recommended to combine license files?

Many system administrators, especially for larger sites, prefer to combine license files to ease administration of FLEX lm licenses. It's purely a matter of preference.

D.1.3 Does FLEX lm handle dates in the year 2000 and beyond?

Yes. The FLEX lm date format uses a four-digit year. Dates in the 20th century (19xx) can be abbreviated to the last two digits of the year (xx), and use of this feature is quite widespread. Dates in the year 2000 and beyond must specify all four year digits.

D.2 FLEXlm Versions

D.2.1 I have products from several companies at various FLEXlm version levels. Do I have to worry about how these versions work together?

If you're not combining license files from different vendors, the simplest thing to do is make sure you use the tools that are shipped by each vendor.

lmgrd will always correctly support older versions of vendor daemons and applications, so it's *always* safe to use the latest version of lmgrd and the lmutil/LMTOOLS utilities. If you've combined license files from two vendors, you *must* use the latest version of lmgrd.

If you've received two versions of a product from the same vendor, you *must* use the latest vendor daemon they send you. An older vendor daemon with a newer client will cause communication errors.

Please ignore letters appended to FLEXlm versions, for example, the "d" in v2.4d. The appended letter indicates a patch, and does NOT indicate any compatibility differences. In particular, some elements of FLEXlm didn't require certain patches, so a v2.4 lmgrd will work successfully with a v2.4b vendor daemon. See also Section G.1, "Version Compatibility and Components."

D.2.2 I've received a new copy of a product from a vendor, and it uses a new version of FLEXlm. Is my old license file still valid?

Yes. Older FLEXlm license files are always valid with newer versions of FLEXlm.

D.2.3 I've received a new license file, and the format is different from the old one I had from the same vendor? Why? Are they compatible?

As of v3.0, FLEXlm has an optional new format for license files. FLEXlm products always understand older versions; therefore, the pre-v3.0 files are understood by every FLEXlm version. However, your old applications (pre-FLEXlm v3.0) will not be able to use the new license file. See also Section 3.2, "License File Format."

D.3 Using FLEXlm

D.3.1 Does FLEXlm work across the Internet?

Yes. A server on the Internet will serve licenses to anyone else on the Internet. This can be limited with the `INTERNET=` attribute on the `FEATURE` line, which limits access to a range of Internet addresses. You can also use the `INCLUDE` and `EXCLUDE` options in the daemon option file to allow (or deny) access to clients running on a range of Internet addresses.

D.3.2 Does FLEXlm work with Internet firewalls?

Many firewalls require that port numbers be specified to the firewall. FLEXlm v5 `lmgrd` supports this.

D.3.3 If my client dies, does the server free the license?

Yes, unless the client's whole system crashes, or becomes disconnected from the network. Assuming communications is TCP, the license is automatically freed immediately. If communications are UDP, then the license is freed after the UDP timeout, which is set by each vendor, but defaults to 45 minutes. UDP communications is normally only set by the end user, so TCP should be assumed. If the whole system crashes, then the license is not freed, and you should use `lmremove` to free the license.

D.3.4 What happens when the license server dies?

FLEXlm applications send periodic heartbeats to the server to discover if it has died. What happens when the server dies is then up to the application. Some will simply continue periodically attempting to re-checkout the license when the server comes back up. Some will attempt to re-checkout a license a few times, and then, presumably with some warning, exit. Some GUI applications will present pop-ups to the user periodically letting them know the server is down and needs to be restarted.

D.3.5 How do you tell if a port is already in use?

99.44% of the time, if it's in use, it's because `lmgrd` is already running on the port—or was recently killed, and the port isn't freed yet. Assuming this is not the case, then use `telnet host port`—if it says “Can't connect,” it's a free port.

D.3.6 Does FLEXlm require root permissions?

No. There is no part of FLEXlm, `lmgrd`, vendor daemon, or application, that requires root permissions. In fact, it is *strongly recommended* that you do not run the license server (`lmgrd`) as “root,” since root processes can introduce

security risks. If `lmgrd` must be started from the root user (for example, in a system boot script), we recommend that you use the `su` command to run `lmgrd` as a non-privileged user:

```
su username -c "lmgrd_path -c license_file_path -l debug_log_path"
```

where `username` is a non-privileged user, and the paths are the correct paths to `lmgrd`, the license file, and the debug log file. You will have to ensure that the vendor daemons listed in the license file have execute permissions for `username`. The paths to all the vendor daemons in the license file are listed on each DAEMON line.

D.3.7 Is it OK to run `lmgrd` as “root” (UNIX only)?

It is not prudent to run any command, particularly a daemon, as root on UNIX, as it may pose a security risk to the operating system. Therefore, we recommend that `lmgrd` be run as a non-privileged user (not “root”). If you are starting `lmgrd` from a boot script, we recommend that you use:

```
su username -c "umask 022; lmgrd..."
```

to run `lmgrd` as a non-privileged user.

D.3.8 Does FLEXlm licensing impose a heavy load on the network?

No, but partly this depends on the application, and end user’s use. A typical checkout request requires five messages and responses between client and server, and each message is <150 bytes.

When a server is not receiving requests, it requires virtually no CPU time.

When an application, or `lmstat`, requests the list of current users, this can significantly increase the amount of networking FLEXlm uses, depending on the number of current users.

Also, prior to FLEXlm v5, use of `port@host` can increase network load, since the license file is downloaded from the server to the client. `port@host` should be, if possible, limited to small license files (say, <50 features). In v5, `port@host` actually *improves* performance.

D.3.9 Does FLEXlm work with NFS?

Yes. FLEXlm has no direct interaction with NFS. FLEXlm uses an NFS-mounted file like any other application.

D.3.10 Does FLEXlm work with ATM, ISDN, Token-Ring, etc.

In general, these have no impact on FLEXlm. FLEXlm requires TCP/IP. So long as TCP/IP works, FLEXlm will work.

D.3.11 Does FLEXlm work with subnets, fully qualified names, multiple domains, etc.?

Yes, although this behavior was improved in v3.0, and v6.0.

When a license server and a client are located in different domains, fully qualified host names have to be used. A “fully qualified host name” is of the form *node.domain*, where *node* is the local host name (usually returned by the `hostname` command or `uname -n`) and *domain* is the Internet domain name, e.g., “globes.com.”

To ensure success with FLEXlm across domains, do the following:

1. Make the sure the fully qualified host name is the name on the SERVER line of the license file.
2. Make sure ALL client nodes, as well as the server node, are able to `telnet` to that fully qualified host name. For example, if the host is locally called “speedy,” and the domain name is “corp.com,” local systems will be able to logon to “speedy” via `telnet speedy`. But very often, `telnet speedy.corp.com` will fail locally. Note that this `telnet` command will always succeed on hosts in other domains (assuming everything is configured correctly), since the network will resolve “speedy.corp.com” automatically.
3. Finally, there must be an alias for “speedy” so it’s also known locally as “speedy.corp.com.” This alias is added to the `/etc/hosts` file, or if NIS/Yellow Pages are being used, then it will have to be added to the NIS database. This requirement goes away in version 3.0 of FLEXlm.

If all components (application, `lmgrd` and vendor daemon) are v6.0 or higher, no aliases are required; the only requirement is that the fully qualified domain name, or IP address, is used as a host name on the SERVER, or as a host name in the `LM_LICENSE_FILE` environment variable (`port@host` or `@host`).

D.3.12 Does FLEXlm work with NIS and DNS?

Yes. However, some sites have broken NIS or DNS, which will cause FLEXlm to fail. In v5 of FLEXlm, NIS and DNS can be avoided to solve this problem. In particular, sometimes DNS is configured for a server that’s not current available (e.g., a dial-up connection from a PC). Again, if DNS is configured, but the server is not available, FLEXlm will fail.

On PCs, if a checkout seems to take three minutes and then fails, this is usually because the system is configured for a dial-up DNS server which is not currently available. The solution here is to turn off DNS.

Finally, host names must NOT have periods in the name. These are not legal host names, although PCs will allow you to enter them, and they will not work with DNS.

D.3.13 We're using FLEXlm over a wide-area network. What can we do to improve performance?

FLEXlm network traffic should be minimized. With the most common uses of FLEXlm, traffic is negligible. In particular, checkout, checkin, and heartbeats use very little networking traffic. There are two items, however, which can send considerably more data and should be avoided or used sparingly:

- `lmstat -a` should be used sparingly. `lmstat -a` should not be used more than, say, once every 15 minutes, and should be particularly avoided when there's a lot of features, or concurrent users, and therefore a lot of data to transmit; say, more than 20 concurrent users or features.
- Prior to FLEXlm v5, the `port@host` mode of the `LM_LICENSE_FILE` environment variable should be avoided, especially when the license file has many features, or there are a lot of license files included in `LM_LICENSE_FILE`. The license file information is sent via the network, and can place a heavy load. Failures due to `port@host` will generate the error `LM_SERVNOREADLIC (-61)`.

D.4 Windows Questions

D.4.1 What PC Platforms are supported?

FLEXlm v7.2 supports Windows 95/98, 2000, and NT.

Note: Networking is required on all 32-bit versions.

D.4.2 Will the Server run on Windows 95?

Yes.

FLEXlm Error Codes

E.1 Error Message Format

FLEXlm error messages presented by applications have the following components:

- FLEXlm Error Number—a negative number starting at -1.
- FLEXlm Error Text—short sentence (< 80 characters) summarizing problem.
- FLEXlm Error Explanation (optional)—short paragraph (3-5 lines) explaining problem and possible solutions or workarounds.
- FLEXlm Minor Error Number—a positive number starting at 1. These numbers are unique error identifiers and are used by FLEXlm ISVs for more advanced support assistance. Their meaning is not documented.
- System Error Number (optional)—a UNIX or Windows OS error code last set by the operating system.
- System Error Explanation (optional)—a short sentence (< 80 characters) explaining the system error.
- Other supporting information (optional)

Error messages were improved in v6. FLEXlm Error Explanation, and supporting information are only available in applications using v6.0+.

These error messages may occur in two formats available with FLEXlm or may appear in a format customized by the application.

E.1.1 Format 1 (short):

```
FLEXlm error text (-lm_errno, minor_num[:sys_errno]) [sys_error_text]
```

The system error information may be missing.

Example:

```
Can't connect to license server (-15,12:61) Connection refused
```

E.1.2 Format 2 (long—version 6+):

```
FLEXlm error text
  FLEXlm error explanation
[Optional Supporting information]
FLEXlm error: -lm_errno, minor_num. [System Error: sys_errno]
["system_error_text"]
```

Example:

```
Cannot connect to license server
  The server (lmgrd) has not been started yet, or
  the wrong port@host or license file is being used, or the
  port or hostname in the license file has been changed.
Feature:          f1
Server name:      localhost
License path:     @localhost:license.dat:./*.lic
FLEXlm error:    -15,12. System Error: 61 "Connection refused"
```

E.2 Error Code Descriptions

Errors marked with an “*” indicates errors which should not appear in shipping software. These are errors intended to help the programmer incorporate FLEXlm in their product, and should be fixed before shipping.

Errors marked with “+” indicate errors due to an operating system failure.

Error	Description
-1	Cannot find license file.
-2	Invalid license file syntax.
-3	No server for this feature.
-4	Licensed number of users already reached.
-5	No such feature exists.
-6	No port number in license file and FLEXlm service does not exist. (pre-v6 only)
-7	No socket connection to license manager service.
-8	Invalid (inconsistent) license key or signature. The license key/signature and data for the feature do not match. This usually happens when a license file has been altered.

- 9 Invalid host.
The hostid of this system does not match the hostid specified in the license file.
- 10 Feature has expired.
- 11 Invalid date format in license file.
- 12 Invalid returned data from license server.
- 13 No SERVER lines in license file.
- 14 Cannot find SERVER host name in network database.
The lookup for the host name on the SERVER line in the license file failed. This often happens when NIS or DNS or the hosts file is incorrect. Workaround: Use IP address (e.g., 123.456.789.123) instead of host name.
- 15 Cannot connect to license server.
The server (*lmgrd*) has not been started yet, or the wrong *port@host* or license file is being used, or the port or host name in the license file has been changed.
- 16 Cannot read data from license server.
- 17 Cannot write data to license server.
- 18 License server does not support this feature.
- 19 Error in select system call.
- 20 [Obsolete]
- 21 License file does not support this version.
- 22 Feature checkin failure detected at license server.
- 23 License server temporarily busy (new server connecting).
- 24 Users are queued for this feature.
- 25 License server does not support this version of this feature.
- 26 Request for more licenses than this feature supports.

Error Code Descriptions

-27	[Obsolete]
-28	[Obsolete]
-29	Cannot find ethernet device.
-30	Cannot read license file.
-31	Feature start date is in the future.
-32	No such attribute.
-33	Bad encryption handshake with daemon.
-34	Clock difference too large between client and server.
-35	In the queue for this feature.
-36	Feature database corrupted in daemon.
-37	Duplicate selection mismatch for this feature.
-38	User/host on EXCLUDE list for feature.
-39	User/host not on INCLUDE list for feature.
-40	Cannot locate dynamic memory.
-41	Feature was never checked out.
-42	Invalid parameter.
-43	* No FLEXlm key data supplied in initializing call.
-44	* Invalid FLEXlm key data supplied.
-45	* FLEXlm function not available in this version.
-46	[Obsolete]
-47	Clock setting check not available in daemon.
-48	* FLEXlm platform not enabled.
-49	* Date invalid for binary format.
-50	* FLEXlm key data has expired.
-51	* FLEXlm not initialized.

- 52 FLEXlm vendor daemon did not respond within timeout interval.
- 53 Checkout request rejected by vendor-defined checkout filter.
- 54 No FEATURESET line in license file.
- 55 Incorrect FEATURESET line in license file.
- 56 Cannot compute FEATURESET data from license file.
- 57 + socket() call failed.
- 58 [Obsolete]
- 59 Message checksum failure.
- 60 Server message checksum failure.
- 61 Cannot read license file data from server.
- 62 Network software (TCP/IP) not available.
- 63 You are not a license administrator.
- 64 lmremove request before the minimum lmremove interval.
- 65 * Unknown VENDORCODE struct type passed to lm_init().
- 66 * FLEXlm include file/library version mismatch.
- 67 [Obsolete]
- 68 [Obsolete]
- 69 [Obsolete]
- 70 [Obsolete]
- 71 Invalid TZ environment variable.
- 72 * Old VENDORCODE (three-word) struct type passed to lm_init().
- 73 Local checkout filter rejected request.

Error Code Descriptions

- 74 Attempt to read beyond end of license file path.
- 75 + SYS\$SETIMR call failed (VMS).
- 76 Internal FLEXlm error - please report to GLOBEtrouter Software.
- 77 Bad version number - must be floating-point number with no letters.
- 78 * FLEXlm internal error -78.
- 79 * FLEXlm internal error -79.
- 80 * FLEXlm internal error -80.
- 81 * FLEXlm internal error -81.
- 82 Invalid PACKAGE line in license file.
- 83 FLEXlm version of client newer than server.
- 84 USER_BASED license has no specified users - see server log.
- 85 License server doesn't support this request.
- 86 License object already in use (Java only).
- 87 Checkout exceeds MAX specified in options file.
- 88 System clock has been set back.
- 89 This platform not authorized by license.
- 90 Future license file format or misspelling in license file. The file was issued for a later version of FLEXlm than this program understands.
- 91 ENCRYPTION_SEEDS are non-unique.
- 92 Feature removed during lmreread, or wrong SERVER line hostid.

- 93 This feature is available in a different license pool. This is a warning condition. The server has pooled one or more INCREMENT lines into a single pool, and the request was made on an INCREMENT line that has been pooled.
- 94 Attempt to generate license with incompatible attributes.
- 95 Network connect to `this_host` failed.
The license file indicates `this_host`, and the server is not running on this host. If it's running on a different host, `this_host` should be changed to the correct host.
- 96 Server node is down or not responding.
See the system administrator about starting the server, or make sure that you're referring to the right host (see `LM_LICENSE_FILE` environment variable).
- 97 The desired vendor daemon is down.
1) Check the `lmgrd` log file, or 2) Try `lmreread`.
- 98 This FEATURE line can't be converted to decimal format.
- 99 The decimal format license is typed incorrectly.
- 100 Cannot remove a linger license.
- 101 All licenses are reserved for others.
The system administrator has reserved all the licenses for others. Reservations are made in the options file. The server must be restarted for options file changes to take effect.
- 102 [Unused]
- 103 [Unused]
- 104 [Unused]
- 105 [Unused]
- 106 License server out of network connections.
The vendor daemon can't handle any more users. See the debug log for further information.

Error Code Descriptions

-107	[Unused]
-108	[Unused]
-109	[Unused]
-110	Dongle not attached, or can't read dongle. Either the hardware dongle is unattached, or the necessary software driver for this dongle type is not installed.
-112	Missing dongle driver. In order to read the dongle hostid, the correct driver must be installed. These drivers are available at http://www.globetrotter.com or from your software vendor.
-113	FLEXlock checkouts attempted. Only one checkout is allowed with FLEXlock-enabled apps.
-114	SIGN= attribute required. This is probably because the license is older than the application. You need to obtain a SIGN= version of this license from your vendor.
-115	Error in Public Key package.

The Debug Log File

FLEXlm daemons generate debug log files in the following format:

hh:mm:ss (daemon) message

where:

hh:mm:ss Time that the message was logged.

daemon Either `lmgrd` or the vendor daemon name. In the case where a single copy of the daemon cannot handle all of the requested licenses, an optional “_” followed by a number indicates that this message comes from a forked daemon.

message The text of the message.

The debug log files can be used to:

- Diagnose configuration problems
- Diagnose daemon software errors

Note: A debug log file cannot be used for usage reporting with `SAMreport`.

F.1 Informational Messages

Connected to *host*

This daemon is connected to its peer on *host*.

CONNECTED, master is *host*

The license daemons log this message when a quorum is up and everyone has selected a master.

DENIED: *num_lic feature to user*

user was denied access to *num_lic* licenses of *feature*.

EXITING DUE TO SIGNAL *nnn*

EXITING with code *nnn*

All daemons list the reason that the daemon has exited.

EXPIRED: *feature*

feature has passed its expiration date.

IN: “*feature*” *user* (*num_lic* licenses)

user has checked in *num_lic* licenses of *feature*.

Lost connection to *host*

A daemon can no longer communicate with its peer on node *host*, which can cause the clients to have to reconnect, or cause the number of daemons to go below the minimum number, in which case clients may start exiting. If the license daemons lose the connection to the master, they will kill all the vendor daemons; vendor daemons will shut themselves down.

Lost quorum

The daemon lost quorum, so will process only connection requests from other daemons.

MULTIPLE *vendor* servers running. Please kill, and restart license daemon.

The license daemon has detected that multiple licenses for vendor daemon *vendor* are running. The user should kill all *vendor* processes and restart the license daemon.

OUT: “*feature*” *user* (*num_lic* licenses)

user has checked out *num_lic* licenses of *feature*.

RESERVE *feature* for USER *user*

RESERVE *feature* for HOST *host*

A license of *feature* is reserved for either *user* or *host*.

REStarted *vendor* (internet port *nnn*)

Vendor daemon *vendor* was restarted at Internet port *nnn*.

Retrying socket bind (address in use)

The license servers try to bind their sockets for approximately six minutes if they detect “address in use” errors.

Selected (EXISTING) master *host*.

This license daemon has selected an existing master *host* as the master.

SERVER shutdown requested.

A daemon was requested to shut down via a user-generated `kill` command.

Server started on *host* for: “*feature_list*”

A (possibly new) server was started for the features listed.

Shutting down *vendor*

The license manager daemon is shutting down the vendor daemon *vendor*.

SIGCHLD received. Killing child servers.

A vendor daemon logs this message when a shutdown was requested by the license daemon.

Started *vendor*

The license manager daemon logs this message whenever it starts a new vendor daemon.

Trying to connect to *host*

The daemon is attempting a connection to *host*.

F.2 Configuration Problem Messages***host*: Not a valid server host, exiting**

This daemon was run on an invalid host name.

***host*: Wrong hostid, exiting**

The hostid is wrong for *host*.

BAD CODE for *feature*

The specified feature name has a bad license key or signature. It was probably typed in wrong, or modified by the end user.

CANNOT OPEN options file *file*

The options file specified in the license file could not be opened.

Couldn't find a master

The daemons could not agree on a master.

License daemon: lost all connections

This message is logged when all the connections to a server are lost, which often indicates a network problem.

Lost lock, exiting

Error closing lock file

Unable to re-open lock file

The vendor daemon has a problem with its lock file, usually because of an attempt to run more than one copy of the daemon on a single node. Locate the other daemon that is running via a `ps` command, and kill it with `kill -9`.

No DAEMON line for *vendor*

The license file does not contain a DAEMON or VENDOR line for *vendor*.

No DAEMON lines, exiting

The license daemon logs this message if there are no DAEMON or VENDOR lines in the license file. Because there are no vendor daemons to start, there is nothing for the license daemon to do.

No features to serve!

A vendor daemon found no features to serve. This could be caused by a corrupted or incorrectly entered license file.

UNSUPPORTED FEATURE request: *feature* by *user*

The user has requested a feature that this vendor daemon does not support. This can happen for a number of reasons: the license file is bad, the feature has expired, or the daemon is accessing the wrong license file.

Unknown host: *host*

The host name specified on a SERVER line in the license file does not exist in the network database (probably `/etc/hosts`).

F.3 Daemon Software Error Messages

accept: message

An error was detected in the “accept” system call.

Can't allocate server table space

A malloc error. Check swap space.

Connection to *host* TIMED OUT

The daemon could not connect to *host*.

Illegal connection request to *vendor*

A connection request was made to *vendor*, but this vendor daemon is not *vendor*.

read: error message

An error in a “read” system call was detected.

select: message

An error in a “select” system call was detected. This is usually a sign of a system networking failure.

Server exiting

The server is exiting. This is normally due to an error.

FLEXlm Versions

G.1 Version Compatibility and Components

In general, always use the latest `lmgrd` and `lmutil/LMTOOLS`, which are available from <http://www.globetrotter.com>, and you'll automatically enjoy many of the enhancements available in the most recent versions. However, some enhancements require upgraded vendor daemons, and yet others require upgraded client applications. Given the following components:

- `lmgrd`
- `lmutil` (includes `lmstat`, `lmdown`, etc., and `LMTOOLS` on Windows)
- Vendor daemon
- License file

the rules about compatibility can be summarized as follows:

Version of `lmutil` must be \geq

Version of `lmgrd`, which must be \geq

Version of vendor daemon, which must be \geq

Version of client application, which must be \geq

Version of license file format

Except for the license file, you can use `lmver` to discover the version of all these components. For the vendor daemon, `lmgrd`, and `lmutil`, you can also use the `-v` argument to print the version.

G.2 How to Tell the License File Version

The following rules apply to individual FEATURE, INCREMENT or UPGRADE lines. It's possible to have a mix of versions in a single file. Only the features that a particular application checks out determine the version of the license for that feature.

Version 2	Blank quotes or a quoted string at the end of the FEATURE line.
>= Version 3	INCREMENT or UPGRADE line.
>= Version 4	OVERDRAFT, DUP_GROUP, INTERNET, or PACKAGE appear.
>= Version 5	SUPERSEDE, ISSUED, USER_BASED, HOST_BASED, or SN appear.
>= Version 6	START appears.
>= Version 7.1	SIGN= attribute appears.

v1.0—1988

First FLEX lm Release, containing all the basic FLEX lm features

v1.5—FEBRUARY 1990

First widely used version including DEMO

v2.1—MARCH 1991

- Improved TIMEOUT support
- Improved ethernet hostid support

v2.21—NOVEMBER 1991

- Added support for many platforms and some platform-specific improvements, such as hostid
- Hostid ANY added

v2.26—MARCH 1992 (USED ONLY BY SUN)

- Added license lingering

v2.4—DECEMBER 1992

- Added “use-all-feature-lines” capability for incremental license distribution
- Enhanced vendor customization routines
- Enhanced end-user options file
- Added new hostid types: USER, HOSTNAME, and DISPLAY
- Added *port@host* to locate license file —downloads license file from server

v2.61—MARCH 1993 (USED ONLY BY SUN)

- Added INCREMENT and UPGRADE lines to license file

v3.0—MAY 1994

- INCREMENT and UPGRADE behavior changed and improved
- Added UDP protocol support
- Added `uname -i` hostid for HP
- Added multiple jobs for enhanced support of `LM_LICENSE_FILE` environment variable as a license file list
- New, optional license file format with *keyword=value* syntax for optional new features, including: `asset_info`, `ISSUER`, and `NOTICE`, “\” license file continuation character, 2048 character limit per feature

v4.0—DECEMBER 1994

- Removed use of floating point, for enhanced reliability
- FEATURE line additions: `ck` (for use with `lmcksum`), `OVERDRAFT`, `DUP_GROUP`, `INTERNET` hostid
- PACKAGE line
- License Finder
- `lmdiag` and `FLEXLM_DIAGNOSTICS` for end-user diagnostics

v4.1—MAY 1995

- Performance improvements and new platform support

v4.1—PATCH RELEASE 6, OCTOBER 1995

- PC patch release for Windows 95 with various performance improvements

v5.0—MARCH 1996

- Improved *port@host* behavior—client application doesn’t read license file
- Automatic *port@host* via `USE_SERVER` line in license file
- Hostid lists—lock a feature to several hostids

- New FEATURE attributes: SN (serial number), USER_BASED, HOST_BASED, MINIMUM, SUPERSEDE, ISSUED (issued date), CAPACITY (charging based on system capacity)
- Optional avoidance of NIS and DNS via IP address instead of host name
- Improved report log file format
- Server, upon startup, notifies of licenses that will expire within two weeks
- Improved end-user options file functionality

v5.11—FEBRUARY 1997

- SUPERSEDE lists, PLATFORMS= license attribute,
- new end-user options: MAX, TIMEOUTALL
- Windows control panel added
- Windows license generator GENLIC added

v5.12—APRIL 1997

- Performance improvements and new platform support

v6.0—SEPTEMBER 1997

- `lmgrd` can read multiple license files
- FLEXlm license directory support: `*.lic` automatically used
- License files require no editing for use at the end-user site
- Optional path on DAEMON/VENDOR line; `PATH` variable used
- Decimal license format, with `lminstall` utility for typing in licenses
- FEATURE lines are shorter, easier to understand and type in
- PACKAGE lines can be shipped in separate files that never require user editing
- Default port numbers make SERVER line port number optional
- Default end-user options file path
- `this_host` host name supported on SERVER line
- `VENDOR_LICENSE_FILE` supported (e.g., `GSI_LICENSE_FILE`)
- `@host` supported where default port numbers are used
- Windows only: user prompted for license file or license server name
- License files are optionally case insensitive
- `lmdown` and `lmreread` accept `-vendor vendor` argument
- `START=dd-mm-yyyy` optional license attribute

v6.1—JUNE 1998

- Performance improvements

v7.0—AUGUST 1999

- License Certificate Manager support for automatic license fulfillment
- Support for “try-before-you-buy” licensing
- License file handles inserted newlines from emailers
- License lines automatically optimally sorted
- Improved LMTOOLS interface for Windows
- `lmgrd`, when run at command line on Windows, runs in background by default
- Improved three-server redundancy reliability (v7 vendor daemon and `lmgrd`)
- `lmreread` and `lmdown` take `-all` argument to shut down or reread all `lmgrds`
- Support registry (Windows) and `$HOME/.flexlmrc` for `FLEXlm` environment variables
- Automatically install license path in registry or `$HOME/.flexlmrc` after successful checkout
- Options support for `LM_PROJECT` with `PROJECT`
- Performance improvements, especially for Windows NT
- Intel Pentium III CPU-ID (v7.0d+, November 1999)

v7.1—AUGUST 2000

- Security enhancements
- `SIGN=` attribute in license

v7.2—DECEMBER 2000

- Performance enhancements

How to Tell the License File Version

Index

A

- ANY hostid 80
- application, what happens when dies 96
- asset_info 31

C

- checksum 64
- ck 31
- combining license files 94
- concurrent license 35
- configuring FLEXlm files 15
- converting license formats 70
- creating options file 48

D

- DAEMON line 24
- dates, Y2K 94
- debug log file
 - format 108
 - rotating to save space 43
- debugging license server 82
- decimal format licenses 70
- DEMO hostid 80
- diagnosing checkout problems
 - troubleshooting
 - checkouts 64
- disabling
 - lmdown 68
 - lmremove 68
- DISK_SERIAL_NUMBER hostid 80
- DISPLAY
 - hostid 80
 - type 51
- dist_info 31
- DUP_GROUP 29

E

- enabling report log 56
- environment variables
 - FLEXLM_BATCH 93
 - FLEXLM_DIAGNOSTICS 93
 - LM_LICENSE_FILE 93
 - LM_PROJECT 93
 - setting 92
 - VENDOR_LICENSE_FILE 93
- error code
 - descriptions 101
 - format 100
- EXCLUDE 51
- EXCLUDEALL 52
- expiration date 28

F

- feature
 - hostid 29
 - listing users 74
 - name 28
 - version 28
- FEATURE line 26
 - asset_info 31
 - ck 31
 - dist_info 31
 - DUP_GROUP 29
 - expiration date 28
 - feature hostid 29
 - feature name 28
 - feature version 28
 - HOST_BASED 30
 - HOSTID 29
 - ISSUED 30
 - ISSUER 30
 - license count 28
 - license key 28
 - NOTICE 30
 - OVERDRAFT 30
 - PLATFORMS 30

- serial number 30
- SIGN 28
- signature 28
- SN 30
- START 30
- SUPERSEDE 30
- syntax 27
- USER_BASED 30
- user_info 31
- v2 vendor string 29
- vendor daemon name 28
- vendor_info 31
- VENDOR_STRING 30
- FLEXID hostid 80
- FLEXlm
 - across Internet 96
 - and ATM 97
 - and DNS 98
 - and domains 98
 - and firewalls 96
 - and ISDN 97
 - and NFS 97
 - and NIS 98
 - and subnets 98
 - and WAN performance 99
 - components 12
 - configuration 15
 - getting started checklist 15
 - installing client applications 15
 - network load 97
 - version compatibility 95
- FLEXlm Programmers Guide 10
- FLEXlm Reference Manual 10
- FLEXLM_BATCH 93
- FLEXLM_DIAGNOSTICS 83
 - level 1 83
 - level 2 84
 - level 3 85
- floating license 35

G

- GROUP type 52

H

- HOST type 50
- host, SERVER line 24
- HOST_BASED 30
- HOST_GROUP type 53
- HOSTID 29
- hostid
 - ANY 80
 - DEMO 80
 - DISK_SERIAL_NUMBER 80
 - DISPLAY 80
 - FLEXID 80
 - HOSTNAME 81
 - ID 81
 - ID_STRING 81
 - INTERNET 81
 - SERVER line 24
 - special 80
 - table by platform 79
 - USER 81
- HOSTNAME hostid 81

I

- ID hostid 81
- ID_STRING hostid 81
- INCLUDE 53
- INCLUDEALL 54
- INCREMENT line 26
- installing client applications 15
- INTERNET
 - hostid 81
 - type 51
- ISSUED 30
- ISSUER 30

L

license

- concurrent 35
- floating 35
- mixed 36
- network license 35
- node-locked 35

license count 28

license directory 19

license file

- checksum 64
- combining multiple 94
- compatibility between different versions 39
- DAEMON line 24
- decimal format 36
- expected location 13
- FEATURE line 26
- format 22
- frequently asked questions 94
- how to combine 38
- INCREMENT line 26
- list, for redundancy and multiple vendors 41
- LM_LICENSE_FILE 13
- lminstall 70
- order of lines 37
- overview 13
- PACKAGE line 31
- rereading after an update 73
- SERVER lines 39
- specifying location 18
- types 34
- UPGRADE line 34
- USE_SERVER line 26
- VENDOR line 24
- with multiple servers 19

license file list 19, 40, 41

license key 28

license manager daemon 12

license request process 14

license server

- and Windows 95 99
- debugging 82
- deciding number of nodes 45
- disk space used 43
- sockets used 42
- what happens when dies 96

LINGER 54

LM_LICENSE_FILE 93

- license file list 41
- syntax 21
- to reference multiple files 14

LM_PROJECT 93

- reporting on project 56
- use in options file 51

lmcksum, syntax 64

lmdiag

- syntax 64
- troubleshooting 64

lmdown

- disabling 68
- restricting access 67
- syntax 66

lmgrd

- and redundant servers 19
- combining license files 94
- compatibility between versions 40
- debug log file 108
- license file list support 38
- memory usage 44
- multiple license files 38
- multiple or single lmgrd processes 39
- nfs_log 68
- overview 12
- ports 96
- root perms on UNIX 96
- running as root 97
- shutting down 66

- starting 18, 67
- starting automatically at boot time
 - 16
- starting debug log 67
- syntax 67
- UNIX startup script 20
- use latest 114
- Windows 21
- lmhostid, syntax 69
- lminstall
 - license file format 70
 - syntax 70
- lmnewlog, syntax 71
- lmremove
 - disabling 68
 - restricting access 67
 - syntax 71
- lmreread
 - restricting access 67
 - syntax 73
- lmstat
 - output for lmreread 74
 - syntax 74
- lmswchr, syntax 76
- LMTTOOLS 77
- lmutil
 - lmcksum 64
 - lmdiag 64
 - lmdown 66
 - lmhostid 69
 - lminstall 70
 - lmnewlog 71
 - lmremove 71
 - lmreread 73
 - lmstat 74
 - lmswchr 76
 - lmver 76
- lmver, syntax 76

M

- MAX 55
- MAX_OVERDRAFT 55
- memory usage, daemons 44
- mixed licenses 36
- multiple license files 38

N

- network bandwidth and FLEXlm 44
- network license 35
- node-locked license 35
- NOLOG 55
- NOTICE 30

O

- options file
 - creating 48
 - DISPLAY type 51
 - examples 59
 - EXCLUDE 51
 - EXCLUDEALL 52
 - GROUP type 52
 - HOST type 50
 - HOST_GROUP type 53
 - INCLUDE 53
 - INCLUDEALL 54
 - INTERNET type 51
 - keywords 49
 - LINGER 54
 - MAX 55
 - MAX_OVERDRAFT 55
 - NOLOG 55
 - overview 17
 - PROJECT type 51
 - read by vendor daemon 58
 - REPORTLOG 56
 - required for HOST_BASED 30
 - required for USER_BASED 30
 - RESERVE 56
 - rules of precedence 58

- TIMEOUT 57
- TIMEOUTALL 58
 - type argument 50
 - USER type 50
- options file path 25
- OPTIONS=SUITE 33
- order of lines in license file 37
- OVERDRAFT 30

P

- PACKAGE line 31
 - OPTIONS=SUITE 33
 - syntax 32
- package suite 33
- PLATFORMS 30
- port number
 - server default range 24
 - SERVER line 24
 - VENDOR line 26
- ports in use 96
- PROJECT type 51

R

- redundant servers
 - selecting server nodes 45
 - separate license files 19
 - SERVER lines 23
- remote disks, guidelines for using 44
- report log file 43
- reporting on project 56
- REPORTLOG 56
- RESERVE 56
- restricting access
 - lmdown 67
 - lmremove 67
 - lmreread 67

S

- SAMreport 56
- SAMsuite Users Guide 10

- SAMwrap Users Guide 10
- SERVER line 23
 - combining license files 39
 - default port numbers 24
 - host 24
 - hostid 24
 - port number 24
 - redundant servers 23
 - syntax 24
- setting environment variables 92
- SIGN 28
- signature 28
- SN 30
- sockets
 - differences under SCO 43
 - number used by license server 42
- specifying location of license file 18
- START 30
- starting lmgrd 18
- status of license server 74
- SUPERSEDE 30
- switching report log
 - lmnewlog 71
 - lmswitchr 76

T

- TIMEOUT 57
 - enabled by developer 57
- TIMEOUTALL 58
- troubleshooting
 - bad code error 88
 - can't connect to server 87
 - execl failed 90
 - lost lock error 91
 - parameter mismatch 88
 - VMS socket bind 89
 - with FLEXLM_DIAGNOSTICS 83
 - with lmdiag 64
 - wrong hostid 86

U

- UPGRADE line, syntax 34
- USE_SERVER line 26
- USER hostid 81
- USER type 50
- USER_BASED 30
- user_info 31

V

- vendor daemon
 - and redundant servers 19
 - debug log file 108
 - lmnewlog 71
 - lmreread 73
 - lmswitchr 76
 - memory usage 44
 - options file 49
 - overview 13
 - restarting 66
 - sockets 42
 - uncounted licenses 47
 - VENDOR_LICENSE_FILE 93
 - version compatibility 40
- vendor daemon name
 - FEATURE line 28
 - VENDOR line 25
- vendor daemon path 25
- VENDOR line 24
 - options file path 25
 - port number 26
 - vendor daemon name 25
 - vendor daemon path 25
- vendor string, v2 29
- vendor.opt 25, 49
- vendor_info 31
- VENDOR_LICENSE_FILE 22, 93
- VENDOR_STRING 30

Y

- Y2K dates 94

W

- Windows 95, and license server 99